

ScopeSim instrument packages for MICADO

Kieran Leschinski, Hugo Buddelmeijer, Oliver Czoske, Miguel Verdugo, Gijs Verdoes-Kleijn, Werner Zeilinger

September 21, 2020

Contents

1	Summary of Effects in Optical Elements:	3
2	OpticalElement: "armazones"	4
2.1	Global properties	4
2.2	Effects	4
2.2.1	AtmosphericTERCurve: "armazones_atmo_default_ter_curve"	4
2.2.2	AtmosphericDispersion: "armazones_atmo_dispersion"	5
2.2.3	SkycalcTERCurve: "armazones_atmo_skycalc_ter_curve"	6
3	OpticalElement: "ELT"	8
3.1	Global properties	8
3.2	Effects	8
3.2.1	SurfaceList: "scope_surface_list"	8
3.2.2	Vibration: "scope_vibration"	9
3.2.3	TERCurve: "eso_combined_reflection"	9
4	OpticalElement: "MAORY"	11
4.1	Global properties	11
4.2	Effects	11
4.2.1	SurfaceList: "maory_surface_list"	11
4.2.2	FieldConstantPSF: "maory_generic_psf"	12
5	OpticalElement: "default_ro"	14
5.1	Global properties	14
5.2	Effects	14
5.2.1	FieldConstantPSF: "relay_psf"	14
5.2.2	SurfaceList: "relay_surface_list"	15
6	OpticalElement: "MICADO"	17
6.1	Global properties	17
6.2	Effects	17
6.2.1	SurfaceList: "micado_static_surfaces"	17
6.2.2	FilterCurve: "micado_filter"	18
6.2.3	NonCommonPathAberration: "micado_ncpas_psf"	19
7	OpticalElement: "MICADO_IMG_LR"	20
7.1	Global properties	20
7.2	Effects	20

7.2.1	SurfaceList: "micado_wide_field_mirror_list"	20
7.2.2	AtmosphericDispersionCorrection: "micado_adc_3D_shift"	21
8	OpticalElement: "MICADO_IMG_HR"	22
8.1	Global properties	22
8.2	Effects	22
8.2.1	SurfaceList: "zoom_mirror_list"	22
8.2.2	AtmosphericDispersionCorrection: "micado_adc_3D_shift"	23
9	OpticalElement: "MICADO_SPEC"	24
9.1	Global properties	24
9.2	Effects	24
9.2.1	SurfaceList: "spec_mode_optics"	24
9.2.2	ApertureMask: "spectroscopic_slit_aperture"	25
10	OpticalElement: "micado_detector_array"	28
10.1	Global properties	28
10.2	Effects	28
10.2.1	DetectorList: "full_detector_array"	28
10.2.2	DetectorList: "detector_window"	29
10.2.3	QuantumEfficiencyCurve: "qe_curve"	30
10.2.4	SummedExposure: "exposure_action"	31
10.2.5	DarkCurrent: "dark_current"	32
10.2.6	LinearityCurve: "detector_linearity"	32
10.2.7	ShotNoise: "shot_noise"	33
10.2.8	PoorMansHxRGReadoutNoise: "readout_noise"	33
11	OpticalElement: "MICADO_simulation_paramters"	35
11.1	Global properties	35
11.2	Effects	35

1 Summary of Effects in Optical Elements:

element	name	class	included	z_orders
armazones	armazones_atmo_default_ter_curve	AtmosphericTERCurve	True	[111, 511]
armazones	armazones_atmo_dispersion	AtmosphericDispersion	True	[231]
armazones	armazones_atmo_skycalc_ter_curve	SkycalcTERCurve	False	[112, 512]
ELT	scope_surface_list	SurfaceList	True	[20, 120, 520]
ELT	scope_vibration	Vibration	True	[244, 744]
ELT	eso_combined_reflection	TERCurve	False	[10, 110, 510]
MICADO	micado_static_surfaces	SurfaceList	True	[20, 120, 520]
MICADO	micado_filter	FilterCurve	True	[114, 214, 514]
MICADO	micado_ncpas_psf	NonCommonPathAberration	True	[241, 641]
micado_detector_array	full_detector_array	DetectorList	False	[90, 290, 390, 490]
micado_detector_array	detector_window	DetectorList	True	[90, 290, 390, 490]
micado_detector_array	qe_curve	QuantumEfficiencyCurve	True	[113, 513]
micado_detector_array	exposure_action	SummedExposure	True	[860]
micado_detector_array	dark_current	DarkCurrent	True	[830]
micado_detector_array	detector_linearity	LinearityCurve	True	[840]
micado_detector_array	shot_noise	ShotNoise	True	[820]
micado_detector_array	readout_noise	PoorMansHxRGReadoutNoise	True	[811]
default_ro	relay_psf	FieldConstantPSF	True	[262, 662]
default_ro	relay_surface_list	SurfaceList	True	[20, 120, 520]
MAORY	maory_surface_list	SurfaceList	True	[20, 120, 520]
MAORY	maory_generic_psf	FieldConstantPSF	True	[262, 662]
MICADO_IMG_LR	micado_wide_field_mirror_list	SurfaceList	True	[20, 120, 520]
MICADO_IMG_LR	micado_adc_3D_shift	AtmosphericDispersionCorrection	True	[632, 232]
MICADO_IMG_HR	zoom_mirror_list	SurfaceList	True	[20, 120, 520]
MICADO_IMG_HR	micado_adc_3D_shift	AtmosphericDispersionCorrection	True	[632, 232]
MICADO_SPEC	spec_mode_optics	SurfaceList	True	[20, 120, 520]
MICADO_SPEC	spectroscopic_slit_aperture	ApertureMask	True	[80, 280, 380]
MICADO_SPEC	micado_spectral_traces	SpectralTraceList	True	[70, 270]
MICADO_SPEC	spec_mode_optics	SurfaceList	True	[20, 120, 520]
MICADO_SPEC	spectroscopic_slit_aperture	ApertureMask	True	[80, 280, 380]
MICADO_SPEC	micado_spectral_traces	SpectralTraceList	True	[70, 270]
MICADO_SPEC	spec_mode_optics	SurfaceList	True	[20, 120, 520]
MICADO_SPEC	spectroscopic_slit_aperture	ApertureMask	True	[80, 280, 380]
MICADO_SPEC	micado_spectral_traces	SpectralTraceList	True	[70, 270]

2 OpticalElement: "armazones"

Element: atmosphere

Alias: ATMO

Description: Atmosphere and location details for Cerro Armazones

2.1 Global properties

```
altitude : 3060
longitude : -70.1918
latitude : -24.5899
temperature : 7
humidity : 0.1
pressure : 0.755
pwv : 2.5
airmass : !OBS.airmass
pupil_angle : !OBS.pupil_angle
pixel_scale : !INST.pixel_scale
element_name : armazones
```

2.2 Effects

Summary of Effects included in this optical element:

element	name	class	included	z_orders
armazones	armazones_atmo_default_ter_curve	AtmosphericTERCurve	True	[111, 511]
armazones	armazones_atmo_dispersion	AtmosphericDispersion	True	[231]
armazones	armazones_atmo_skycalc_ter_curve	SkycalcTERCurve	False	[112, 512]

2.2.1 AtmosphericTERCurve: "armazones_atmo_default_ter_curve"

Included by default: True

File Description: atmospheric emission and transmission

Class Description: <no docstring>

Changes:

- 2019-07-24 (KL) Created file
- 2019-08-09 (KL) Updated values for airmass 1.2, pwv 2.5

Data

Meta-data

```
filename : TER_armazones_default_NIR_IMG.dat
name : armazones_atmo_default_ter_curve
include : True
altitude : 3060
```

```

longitude : -70.1918
latitude  : -24.5899
temperature : 7
humidity  : 0.1
pressure  : 0.755
pwv       : 2.5
airmass   : !OBS.airmass
pupil_angle : !OBS.pupil_angle
pixel_scale : !INST.pixel_scale
element_name : armazones
author    : Kieran Leschinski
source    : skycalc website for standard Armazones conditions
date_created : 2019-07-24
date_modified : 2019-08-09
status     : Design
type       : atmosphere:ter_curve
season     : entire year
time       : entire night
action     : transmission
wavelength_unit : um
emission_unit : ph s-1 m-2 um-1 arcsec-2
z_order     : [111, 511]
ignore_wings : False
wave_min    : !SIM.spectral.wave_min
wave_max    : !SIM.spectral.wave_max
wave_unit   : !SIM.spectral.wave_unit
wave_bin    : !SIM.spectral.spectral_resolution
area        : !TEL.area
area_unit   : m2
position    : 0

```

2.2.2 AtmosphericDispersion: "armazones_atmo_dispersion"

Included by default: True

File Description: atmospheric dispersion

Class Description: Used to generate the wavelength bins based on shifts due to the atmosphere

Changes:

-

Data

Meta-data

```

filename : None
name      : armazones_atmo_dispersion
altitude  : 3060
longitude : -70.1918
latitude  : -24.5899

```

```

    temperature : 7
    humidity : 0.1
    pressure : 0.755
    pwv : 2.5
    airmass : !OBS.airmass
    pupil_angle : !OBS.pupil_angle
    pixel_scale : !INST.pixel_scale
    element_name : armazones
    z_order : [231]
    include : True
    wave_min : !SIM.spectral.wave_min
    wave_mid : !SIM.spectral.wave_mid
    wave_max : !SIM.spectral.wave_max
    sub_pixel_fraction : !SIM.sub_pixel.fraction
    num_steps : 1000

```

2.2.3 SkycalcTERCurve: "armazones_atmo_skycalc_ter_curve"

Included by default: False

File Description: atmospheric spectra pulled from the skycalc server

Class Description: <no docstring>

Changes:

-

Data

Meta-data

```

    filename : None
    name : armazones_atmo_skycalc_ter_curve
    include : False
    altitude : 3060
    longitude : -70.1918
    latitude : -24.5899
    temperature : 7
    humidity : 0.1
    pressure : 0.755
    pwv : 2.5
    airmass : !OBS.airmass
    pupil_angle : !OBS.pupil_angle
    pixel_scale : !INST.pixel_scale
    element_name : armazones
    observatory : armazones
    wmin : 699.9999999999999
    wmax : 2499.999999999995
    wunit : um
    wdelta : 0.09999999999999999
    z_order : [112, 512]

```

```
ignore_wings : False
  wave_min : !SIM.spectral.wave_min
  wave_max : !SIM.spectral.wave_max
wave_unit : !SIM.spectral.wave_unit
  wave_bin : !SIM.spectral.spectral_resolution
    action : transmission
    area : !TEL.area
area_unit : m2
position : 0
```

3 OpticalElement: "ELT"

Element: telescope

Alias: TEL

Description: The extremely large telescope

3.1 Global properties

```
temperature : !ATMO.temperature
element_name : ELT
```

3.2 Effects

Summary of Effects included in this optical element:

element	name	class	included	z_orders
ELT	scope_surface_list	SurfaceList	True	[20, 120, 520]
ELT	scope_vibration	Vibration	True	[244, 744]
ELT	eso_combined_reflection	TERCurve	False	[10, 110, 510]

3.2.1 SurfaceList: "scope_surface_list"

Included by default: True

File Description: list of ELT surfaces

Class Description: <no docstring>

Changes:

- 2018-11-19 (KL) Added meta data, added Action column
- 2019-01-28 (KL) Fixed YAML format in meta data
- 2020-08-17 (KL) Updated M1 and M4 dimensions according to ESO-253082_4 sect 4.7 "all-glass" diameter
- 2020-08-17 (KL) Pegged temperature to the atmosphere

Data

Meta-data

```
filename : LIST_mirrors_ELT.tbl
name : scope_surface_list
temperature : !ATMO.temperature
element_name : ELT
author : Oliver Czoske, Kieran Leschinski
source : ESO ELT DRM, ESO-253082_4
date_created : 2018-11-19
date_modified : 2020-08-17
status : Design - pre MICADO-FDR mirror list
```



```

        outer_unit : m
        inner_unit : m
        angle_unit : degree
    temperature_unit : deg_C
        notes : ['2020-08-17 (KL) Coatings match those described in ESO-2
        z_order : [20, 120, 520]
        include : True
    ignore_wings : False
        wave_min : !SIM.spectral.wave_min
        wave_max : !SIM.spectral.wave_max
        wave_unit : !SIM.spectral.wave_unit
        wave_bin : !SIM.spectral.spectral_resolution
    minimum_throughput : !SIM.spectral.minimum_throughput
        etendue : !TEL.etendue

```

3.2.2 Vibration: "scope_vibration"

Included by default: True

File Description: residual vibration of telescope

Class Description: Creates a wavelength independent kernel image

Changes:

-

Data

Meta-data

```

        filename : None
        name : scope_vibration
    temperature : 7
    element_name : ELT
        fwhm : 0.001
    pixel_scale : 0.004
        z_order : [244, 744]
        include : True
    flux_accuracy : 0.001
    sub_pixel_flag : False
    convolve_mode : full
        wave_key : WAVE0
    normalise_kernel : True
    width_n_fwhms : 4

```

3.2.3 TERCurve: "eso_combined_reflection"

Included by default: False

File Description: single combined reflection curve for clean ELT 5 mirror combination

Class Description: Transmission, Emissivity, Reflection Curve

Changes:

- 2019-11-06 (KL) Converted from .xlsx to .dat file, added ScopeSim meta data
- 2020-07-09 (KL) Added inner and outer dimensions to meta, for use with MICADO-Sci
- 2020-08-17 (KL) Added emissivity column according to ESO-253082_4, sect 4.12.2

Data**Meta-data**

```
filename : TER_ELT_system_20190611.dat
name : eso_combined_reflection
include : False
temperature : !ATMO.temperature
element_name : ELT
temperture : !ATMO.temperature
author : R. Holzloehner
source : See ESO-306070 and ESO-293390 for background.
date_created : 2018-09-18
date_modified : 2019-06-11
type : TERCurve
status : design
action : reflection
outer : 37.3
outer_unit : m
inner : 11.1
inner_unit : m
wavelength_unit : um
notes : ['Baseline coatings.', 'Fresh coatings without contamination']
z_order : [10, 110, 510]
ignore_wings : False
wave_min : !SIM.spectral.wave_min
wave_max : !SIM.spectral.wave_max
wave_unit : !SIM.spectral.wave_unit
wave_bin : !SIM.spectral.spectral_resolution
```

4 OpticalElement: "MAORY"

Element: relay_optics

Alias: RO

Description: MAORY AO relay module

4.1 Global properties

```
temperature : !ATMO.temperature
psf_filename : None
element_name : MAORY
```

4.2 Effects

Summary of Effects included in this optical element:

element	name	class	included	z_orders
MAORY	maory_surface_list	SurfaceList	True	[20, 120, 520]
MAORY	maory_generic_psf	FieldConstantPSF	True	[262, 662]

4.2.1 SurfaceList: "maory_surface_list"

Included by default: True

File Description: list of surfaces in MAORY

Class Description: <no docstring>

Changes:

- 2018-11-19 (KL) Added meta data, changed Dichr. filename
- 2019-01-28 (KL) Fixed YAML format in meta data
- 2020-06-22 (KL) Obsolete. Use LIST_mirrors_maory_mms.tbl from now on.

Data

Meta-data

```
filename : LIST_mirrors_MCAO_MAORY.tbl
name : maory_surface_list
temperature : !ATMO.temperature
psf_filename : None
element_name : MAORY
author : Kieran Leschinski
source : Ciliegi+ 2018 SPIE, "MAORY for ELT - preliminary design o
date_created : 2018-11-19
date_modified : 2018-11-19
status : Design - pre PDR list of MAORY mirrors
type : mirror:list
outer_unit : m
```

```

        inner_unit : m
        angle_unit : degree
    temperature_unit : deg_C
        z_order : [20, 120, 520]
        include : True
    ignore_wings : False
        wave_min : !SIM.spectral.wave_min
        wave_max : !SIM.spectral.wave_max
        wave_unit : !SIM.spectral.wave_unit
        wave_bin : !SIM.spectral.spectral_resolution
    minimum_throughput : !SIM.spectral.minimum_throughput
        etendue : !TEL.etendue

```

4.2.2 FieldConstantPSF: "maory_generic_psf"

Included by default: True

File Description: MAORY field varying MCAO PSF

Class Description: <no docstring>

Changes:

-

Data

Meta-data

```

        filename : PSF_MCAO_ConstPSF_40_18_6.fits
        name : maory_generic_psf
    temperature : 7
    psf_filename : None
    element_name : MAORY
        warning : Default PSF is not Field Varying. See Documentation
        SIMPLE : True
        BITPIX : 8
        NAXIS : 0
        EXTEND : True
        AUTHOR : Kieran Leschinski
    DATE_CRE : 2019-07-30
    DATE_MOD : 2019-07-30
        SOURCE : AnisoCADO
        STATUS : Best guess for a MAORY ConstantPSF with AnisoCADO
        ETYPE : CONSTPSF
        ECAT : -1
        EDATA : 1
        XOFFSET : 0
        YOFFSET : 0
        z_order : [262, 662]
        include : True
    flux_accuracy : 0.001

```

```
sub_pixel_flag : False
convolve_mode  : full
    wave_key   : WAVE0
normalise_kernel : True
```

5 OpticalElement: "default_ro"

Element: relay_optics

Alias: RO

Description: Simple stand-alone relay optics module

5.1 Global properties

```
temperature : !ATMO.temperature
psf_filename : None
element_name : default_ro
```

5.2 Effects

Summary of Effects included in this optical element:

element	name	class	included	z_orders
default_ro	relay_psf	FieldConstantPSF	True	[262, 662]
default_ro	relay_surface_list	SurfaceList	True	[20, 120, 520]

5.2.1 FieldConstantPSF: "relay_psf"

Included by default: True

File Description: SCAO PSF

Class Description: <no docstring>

Changes:

-

Data

Meta-data

```
filename : PSF_SCAO_ConstPSF_0_5off.fits
name : relay_psf
temperature : 7
psf_filename : None
element_name : default_ro
warning : Default PSF is NOT field varying. See documentation.
SIMPLE : True
BITPIX : 8
NAXIS : 0
EXTEND : True
AUTHOR : Kieran Leschinski
DATE_CRE : 2019-07-30
DATE_MOD : 2019-07-30
SOURCE : AnisoCADO
STATUS : Best guess for a standard observations
```

```

        ETYPE : CONSTPSF
        ECAT : -1
        EDATA : 1
        XOFFSET : 0
        YOFFSET : 5
        z_order : [262, 662]
        include : True
    flux_accuracy : 0.001
    sub_pixel_flag : False
    convolve_mode : full
    wave_key : WAVE0
    normalise_kernel : True

```

5.2.2 SurfaceList: "relay_surface_list"

Included by default: True

File Description: list of surfaces in the relay optics

Class Description: <no docstring>

Changes:

- 2018-11-19 (KL) Added meta data
- 2019-01-28 (KL) Fixed YAML format in meta data
- 2020-07-18 (KL) Added all 6 mirrors from the CM16 update pdf
- 2020-07-18 (KL) Pegged temperature to atmosphere

Data

Meta-data

```

    filename : LIST_RO_SCAO_mirrors.dat
    name : relay_surface_list
    temperature : !ATMO.temperature
    psf_filename : None
    element_name : default_ro
    author : Oliver Czoske, Kieran Leschinski
    source : P12_RelayOptics_Status_2020-06-23-MICADO-CM16-RO-v2.pdf
    date_created : 2018-11-19
    date_modified : 2020-08-17
    status : Design - pre FDR list of stand-alone SCAO relay optics mi
    type : mirror:list
    outer_unit : m
    inner_unit : m
    angle_unit : degree
    temperature_unit : deg_C
    z_order : [20, 120, 520]
    include : True
    ignore_wings : False
    wave_min : !SIM.spectral.wave_min

```

```
    wave_max : !SIM.spectral.wave_max  
    wave_unit : !SIM.spectral.wave_unit  
    wave_bin : !SIM.spectral.spectral_resolution  
minimum_throughput : !SIM.spectral.minimum_throughput  
    etendue : !TEL.etendue
```


6 OpticalElement: "MICADO"

Element: instrument

Alias: INST

Description: Effects from the MICADO common optics

6.1 Global properties

```
temperature : -190
element_name : MICADO
```

6.2 Effects

Summary of Effects included in this optical element:

element	name	class	included	z_orders
MICADO	micado_static_surfaces	SurfaceList	True	[20, 120, 520]
MICADO	micado_filter	FilterCurve	True	[114, 214, 514]
MICADO	micado_ncpas_psf	NonCommonPathAberration	True	[241, 641]

6.2.1 SurfaceList: "micado_static_surfaces"

Included by default: True

File Description: surfaces list for wide field optics

Class Description: <no docstring>

Changes:

- {datetime.date(2019, 1, 28): '(KL) Changed column names and added units to header'}
- {datetime.date(2019, 7, 10): '(KL) Shortened the list to only the swappable mirrors'}
- {datetime.date(2020, 8, 25): '(KL) Updated angle_unit to degree from degrees (why has astropy not complained until now?)'}

Data

Meta-data

```
filename : LIST_MICADO_mirrors_static.dat
name : micado_static_surfaces
temperature : -190
element_name : MICADO
author : Kieran Leschinski
source : Ric's SPIE 2018 PPT presentation
date_created : 2018-11-19
date_modified : 2019-07-10
status : Design - pre PDR list of all static MICADO surfaces
type : mirror:list
```

```

        outer_unit : m
        inner_unit : m
        angle_unit : degree
    temperature_unit : deg_C
        z_order : [20, 120, 520]
        include : True
    ignore_wings : False
        wave_min : !SIM.spectral.wave_min
        wave_max : !SIM.spectral.wave_max
        wave_unit : !SIM.spectral.wave_unit
        wave_bin : !SIM.spectral.spectral_resolution
    minimum_throughput : !SIM.spectral.minimum_throughput
        etendue : !TEL.etendue

```

6.2.2 FilterCurve: "micado_filter"

Included by default: True

File Description: transmission curve for filter

Class Description: Other Parameters

Changes:

-

Data

Meta-data

```

        filename : filters/TC_filter_Spec_HK.dat
        name : micado_filter
    temperature : -190
    element_name : MICADO
        filter_name : !OBS.filter_name
    filename_format : filters/TC_filter_{}.dat
    minimum_throughput : 0.000101
        outer : 0.2
        outer_unit : m
        author : Ric Davies
        source : Ric Davies
    date_created : 2017-11-20
    date_modified : 2017-11-20
        status : Design - pre PDR list of filters
        z_order : [114, 214, 514]
        include : True
    ignore_wings : False
        wave_min : !SIM.spectral.wave_min
        wave_max : !SIM.spectral.wave_max
        wave_unit : !SIM.spectral.wave_unit
        wave_bin : !SIM.spectral.spectral_resolution
        action : transmission

```

```
position : -1
wing_flux_level : None
```

6.2.3 NonCommonPathAberration: "micado_ncpas_psf"

Included by default: True

File Description: Effective NCPA induced PSF kernel

Class Description: Needed: pixel_scale

Changes:

- 2018-11-19 (KL) updated meta data to new format

Data

Meta-data

```
filename : INST_MICADO_wavefront_error_budget.dat
name : micado_ncpas_psf
temperature : -190
element_name : MICADO
pixel_scale : 0.004
author : Kieran Leschinski
sources : Ric Davies email
date_created : 2016-11-21
date_modified : 2018-11-19
type : instrument:wavefront_errors_list
status : Idea - based on the WFE budget and emails with Ric
wfe_rms_unit : nm
z_order : [241, 641]
include : True
flux_accuracy : 0.001
sub_pixel_flag : False
convolve_mode : full
wave_key : WAVE0
normalise_kernel : True
kernel_width : None
strehl_drift : 0.02
wave_min : !SIM.spectral.wave_min
wave_max : !SIM.spectral.wave_max
```

7 OpticalElement: "MICADO_IMG_LR"

Element: instrument

Alias: INST

Description: additional effects for the wide-field imaging mode

7.1 Global properties

```
pixel_scale : 0.004
plate_scale : 0.266666666666
element_name : MICADO_IMG_LR
```

7.2 Effects

Summary of Effects included in this optical element:

element	name	class	included	z_orders
MICADO_IMG_LR	micado_wide_field_mirror_list	SurfaceList	True	[20, 120, 520]
MICADO_IMG_LR	micado_adc_3D_shift	AtmosphericDispersionCorrection	True	[632, 232]

7.2.1 SurfaceList: "micado_wide_field_mirror_list"

Included by default: True

File Description: list of extra mirrors needed for the wide field mode

Class Description: <no docstring>

Changes:

- {datetime.date(2019, 1, 28): '(KL) Changed column names and added units to header'}
- {datetime.date(2019, 7, 10): '(KL) Shortened the list to only the swappable mirrors'}

Data

Meta-data

```
filename : LIST_MICADO_mirrors_wide.dat
name : micado_wide_field_mirror_list
pixel_scale : 0.004
plate_scale : 0.266666666666
element_name : MICADO_IMG_LR
author : Kieran Leschinski
source : Ric's SPIE 2018 PPT presentation
date_created : 2018-11-19
date_modified : 2019-07-10
status : Design - pre PDR list of MICADO mirrors for wide-field mo
type : mirror:list
outer_unit : m
inner_unit : m
```

```

        angle_unit : degree
    temperature_unit : deg_C
        z_order : [20, 120, 520]
        include : True
    ignore_wings : False
        wave_min : !SIM.spectral.wave_min
        wave_max : !SIM.spectral.wave_max
        wave_unit : !SIM.spectral.wave_unit
        wave_bin : !SIM.spectral.spectral_resolution
    minimum_throughput : !SIM.spectral.minimum_throughput
        etendue : !TEL.etendue

```

7.2.2 AtmosphericDispersionCorrection: "micado_adc_3D_shift"

Included by default: True

File Description: atmospheric dispersion corrector

Class Description: <no docstring>

Changes:

-

Data

Meta-data

```

    filename : None
        name : micado_adc_3D_shift
    pixel_scale : 0.004
    plate_scale : 0.266666666666
    element_name : MICADO_IMG_LR
        altitude : !ATMO.altitude
        longitude : !ATMO.longitude
        latitude : !ATMO.latitude
        airmass : !OBS.airmass
    temperature : !ATMO.temperature
        humidity : !ATMO.humidity
        pressure : !ATMO.pressure
    pupil_angle : !OBS.pupil_angle
    efficiency : 1
        wave_mid : !SIM.spectral.wave_mid
    quick_adc : True
        z_order : [632, 232]
        include : True

```

8 OpticalElement: "MICADO_IMG_HR"

Element: instrument

Alias: INST

Description: additional effects for the zoom imaging mode

8.1 Global properties

```
pixel_scale : 0.0015
plate_scale : 0.1
element_name : MICADO_IMG_HR
```

8.2 Effects

Summary of Effects included in this optical element:

element	name	class	included	z_orders
MICADO_IMG_HR	zoom_mirror_list	SurfaceList	True	[20, 120, 520]
MICADO_IMG_HR	micado_adc_3D_shift	AtmosphericDispersionCorrection	True	[632, 232]

8.2.1 SurfaceList: "zoom_mirror_list"

Included by default: True

File Description: list of extra mirror needed for the zoom imaging mode

Class Description: <no docstring>

Changes:

- {datetime.date(2019, 1, 28): '(KL) Changed column names and added units to header'}
- {datetime.date(2019, 7, 10): '(KL) Shortened the list to only the swappable mirrors'}

Data

Meta-data

```
filename : LIST_MICADO_mirrors_zoom.dat
name : zoom_mirror_list
pixel_scale : 0.0015
plate_scale : 0.1
element_name : MICADO_IMG_HR
author : Kieran Leschinski
source : Ric's SPIE 2018 PPT presentation
date_created : 2018-11-19
date_modified : 2019-07-10
status : Design - pre PDR list of swappable mirrors for zoom mode
type : mirror:list
ETypes : SURFLIST
EDIM : 1
```

```

        outer_unit : m
        inner_unit : m
        angle_unit : degree
    temperature_unit : deg_C
        z_order : [20, 120, 520]
        include : True
    ignore_wings : False
        wave_min : !SIM.spectral.wave_min
        wave_max : !SIM.spectral.wave_max
        wave_unit : !SIM.spectral.wave_unit
        wave_bin : !SIM.spectral.spectral_resolution
    minimum_throughput : !SIM.spectral.minimum_throughput
        etendue : !TEL.etendue

```

8.2.2 AtmosphericDispersionCorrection: "micado_adc_3D_shift"

Included by default: True

File Description: atmospheric dispersion corrector

Class Description: <no docstring>

Changes:

-

Data

Meta-data

```

    filename : None
        name : micado_adc_3D_shift
    pixel_scale : 0.0015
    plate_scale : 0.1
    element_name : MICADO_IMG_HR
        altitude : !ATMO.altitude
        longitude : !ATMO.longitude
        latitude : !ATMO.latitude
        airmass : !OBS.airmass
    temperature : !ATMO.temperature
        humidity : !ATMO.humidity
        pressure : !ATMO.pressure
    pupil_angle : !OBS.pupil_angle
        wave_mid : !SIM.spectral.wave_mid
    efficiency : 1
    quick_adc : True
        z_order : [632, 232]
        include : True

```

9 OpticalElement: "MICADO_SPEC"

Element: instrument

Alias: INST

Description: additional effects for the spectroscopy mode

9.1 Global properties

```
pixel_scale : 0.004
plate_scale : 0.2666666667
element_name : MICADO_SPEC
```

9.2 Effects

Summary of Effects included in this optical element:

element	name	class	included	z_orders
MICADO_SPEC	spec_mode_optics	SurfaceList	True	[20, 120, 520]
MICADO_SPEC	spectroscopic_slit_aperture	ApertureMask	True	[80, 280, 380]
MICADO_SPEC	micado_spectral_traces	SpectralTraceList	True	[70, 270]

9.2.1 SurfaceList: "spec_mode_optics"

Included by default: True

File Description: list of extra mirrors needed for the spectroscopy mode

Class Description: <no docstring>

Changes:

- {datetime.date(2019, 1, 28): '(KL) Changed column names and added units to header'}
- {datetime.date(2019, 7, 10): '(KL) Shortened the list to only the swappable gratings'}

Data

Meta-data

```
filename : LIST_MICADO_mirrors_spec.dat
name : spec_mode_optics
pixel_scale : 0.004
plate_scale : 0.2666666667
element_name : MICADO_SPEC
author : Kieran Leschinski
source : Ric's SPIE 2018 PPT presentation
date_created : 2018-11-19
date_modified : 2019-07-10
status : Design - pre PDR list of swappable optics for spectroscopy
type : mirror:list
ETYPE : SURFLIST
```



```

        EDIM : 1
    outer_unit : m
    inner_unit : m
    angle_unit : degree
    temperature_unit : deg_C
        z_order : [20, 120, 520]
    include : True
    ignore_wings : False
        wave_min : !SIM.spectral.wave_min
        wave_max : !SIM.spectral.wave_max
        wave_unit : !SIM.spectral.wave_unit
        wave_bin : !SIM.spectral.spectral_resolution
    minimum_throughput : !SIM.spectral.minimum_throughput
        etendue : !TEL.etendue

```

9.2.2 ApertureMask: "spectroscopic_slit_aperture"

Included by default: True

File Description: Slit mask for the short, narrow slit (3 arcsec x 20 mas)

Class Description: Only provides the on-sky window coords of the Aperture

Changes:

- {datetime.date(2019, 7, 10): '(KL) Created the file'}
- {datetime.date(2020, 3, 24): '(KL) Changed geometry to 3000x20mas'}

Data

Meta-data

```

    filename : !OBS.slit_file
        name : spectroscopic_slit_aperture
    pixel_scale : 0.004
    plate_scale : 0.2666666667
    element_name : MICADO_SPEC
        author : Kieran Leschinski
        source : My imagination
    date_created : 2019-07-10
    date_modified : 2019-07-10
        status : Guess - in the train on the way home from CM13
        type : aperture:slit_geometry
    x_unit : arcsec
    y_unit : arcsec
    z_order : [80, 280, 380]
    include : True
    no_mask : True
        angle : 0
        shape : rect
    conserve_image : True
        id : 0

```

```

<SpectralTrace> "list of spectral order trace geometry on the focal plane" : [1.93, 2.46]um : Ext 2 : Aperture
0 : ImagePlane 0 <SpectralTrace> "list of spectral order trace geometry on the focal plane" : [1.45, 1.85]um :
Ext 3 : Aperture 0 : ImagePlane 0 <SpectralTrace> "list of spectral order trace geometry on the focal plane"
: [1.16, 1.48]um : Ext 4 : Aperture 0 : ImagePlane 0 <SpectralTrace> "list of spectral order trace geometry
on the focal plane" : [1.16, 1.39]um : Ext 5 : Aperture 0 : ImagePlane 0 <SpectralTrace> "list of spectral
order trace geometry on the focal plane" : [0.97, 1.23]um : Ext 6 : Aperture 0 : ImagePlane 0 <SpectralTrace>
"list of spectral order trace geometry on the focal plane" : [0.97, 1.23]um : Ext 7 : Aperture 0 : ImagePlane 0
<SpectralTrace> "list of spectral order trace geometry on the focal plane" : [0.83, 1.05]um : Ext 8 : Aperture
0 : ImagePlane 0 <SpectralTrace> "list of spectral order trace geometry on the focal plane" : [0.83, 1.05]um :
Ext 9 : Aperture 0 : ImagePlane 0 <SpectralTrace> "list of spectral order trace geometry on the focal plane"
: [0.83, 0.92]um : Ext 10 : Aperture 0 : ImagePlane 0 <SpectralTrace> "list of spectral order trace geometry
on the focal plane" : [0.73, 0.92]um : Ext 11 : Aperture 0 : ImagePlane 0 <SpectralTrace> "list of spectral
order trace geometry on the focal plane" : [0.73, 0.92]um : Ext 12 : Aperture 0 : ImagePlane 0 <Spectral-
Trace> "list of spectral order trace geometry on the focal plane" : [0.65, 0.82]um : Ext 13 : Aperture 0 :
ImagePlane 0 <SpectralTrace> "list of spectral order trace geometry on the focal plane" : [0.65, 0.82]um : Ext
14 : Aperture 0 : ImagePlane 0 <SpectralTrace> "list of spectral order trace geometry on the focal plane" :
[0.6, 0.74]um : Ext 15 : Aperture 0 : ImagePlane 0 <SpectralTrace> "list of spectral order trace geometry on
the focal plane" : [0.6, 0.73]um : Ext 16 : Aperture 0 : ImagePlane 0 <SpectralTrace> "list of spectral order
trace geometry on the focal plane" : [0.6, 0.67]um : Ext 17 : Aperture 0 : ImagePlane 0 <SpectralTrace>
"list of spectral order trace geometry on the focal plane" : [0.6, 0.67]um : Ext 18 : Aperture 0 : ImagePlane 0
*****

```

Included by default: True

File Description: list of spectral order trace geometry on the focal plane

Class Description: List of spectral trace geometries for the detector plane

Changes:

-

Data

Meta-data

```

filename : !OBS.trace_file
name : micado_spectral_traces
pixel_scale : 0.004
plate_scale : 0.2666666667
element_name : MICADO_SPEC
wave_colname : lam
s_colname : xi
col_number_start : 1
invalid_value : 0
SIMPLE : True
BITPIX : 8
NAXIS : 0
EXTEND : True
FILETYPE : Spectral Layout Definition
AUTHOR : Oliver Czoske
DATE : 2018-09-16
SOURCE : Frank Grupp

```

ORIGDATE : 2018-06-29
STATUS : Design PDR
ECAT : 1
EDATA : 2
DESCRIPT : Maps spectral traces from long slit aperture to detector im
DATE_CRE : 2018-06-29
DATE_MOD : 2019-09-16
HISTORY : 2019-09-16 : (KL) Added aperture-imagePlane table to EXT 1
z_order : [70, 270]
include : True
wave_min : !SIM.spectral.wave_min
wave_max : !SIM.spectral.wave_max
x_colname : x
y_colname : y
dwave : 0.002

10 OpticalElement: "micado_detector_array"

Element: detector

Alias: DET

Description: A set of 9 H4RG detectors

10.1 Global properties

```
image_plane_id : 0
temperature    : -230
               dit : !OBS.dit
               ndit : !OBS.ndit
element_name   : micado_detector_array
```

10.2 Effects

Summary of Effects included in this optical element:

element	name	class	included	z_orders
micado_detector_array	full_detector_array	DetectorList	False	[90, 290, 390, 490]
micado_detector_array	detector_window	DetectorList	True	[90, 290, 390, 490]
micado_detector_array	qe_curve	QuantumEfficiencyCurve	True	[113, 513]
micado_detector_array	exposure_action	SummedExposure	True	[860]
micado_detector_array	dark_current	DarkCurrent	True	[830]
micado_detector_array	detector_linearity	LinearityCurve	True	[840]
micado_detector_array	shot_noise	ShotNoise	True	[820]
micado_detector_array	readout_noise	PoorMansHxRGReadoutNoise	True	[811]

10.2.1 DetectorList: "full_detector_array"

Included by default: False

File Description: MICADO detector array list

Class Description: A description of detector positions and properties

Changes:

- {datetime.date(2017, 8, 12): '(OC) id changed to conform with spectroscopy report'}
- {datetime.date(2018, 7, 26): '(OC) large gap (chips 5 and 6) reduced to 8 mm'}
- {datetime.date(2018, 11, 19): '(KL) updated meta data to new format'}
- {datetime.date(2019, 1, 28): '(KL) moved units into header'}

id	x_cen	y_cen	x_size	y_size	x_len	y_len	pixel_size	angle	gain
1	-63.84	63.84	61.44	61.44	4096	4096	0.015	0.0	1.0
2	0.0	63.84	61.44	61.44	4096	4096	0.015	0.0	1.0

... continued on next page

id	x_cen	y_cen	x_size	y_size	x_len	y_len	pixel_size	angle	gain
3	63.84	63.84	61.44	61.44	4096	4096	0.015	0.0	1.0
4	63.84	0.0	61.44	61.44	4096	4096	0.015	0.0	1.0
5	0.0	0.0	61.44	61.44	4096	4096	0.015	0.0	1.0
6	-69.44	0.0	61.44	61.44	4096	4096	0.015	0.0	1.0
7	-63.84	-63.84	61.44	61.44	4096	4096	0.015	0.0	1.0
8	0.0	-63.84	61.44	61.44	4096	4096	0.015	0.0	1.0
9	63.84	-63.84	61.44	61.44	4096	4096	0.015	0.0	1.0

Data

Meta-data

```

        filename : FPA_array_layout.dat
        name : full_detector_array
        include : False
image_plane_id : 0
    temperature : -230
        dit : !OBS.dit
        ndit : !OBS.ndit
    element_name : micado_detector_array
active_detectors : all
        author : Oliver Czoske
    sources : E-MCD-FPA-572089EB.uda, ELT-TRE-MCD-56300-0011
    date_created : 2017-06-28
    date_modified : 2018-07-26
        type : detector:chip_list
    x_cen_unit : mm
    y_cen_unit : mm
    xhw_unit : mm
    yhw_unit : mm
    x_len_unit : pix
    y_len_unit : pix
    pixsize_unit : mm
    angle_unit : deg
    gain_unit : electron/adu
    z_order : [90, 290, 390, 490]
    pixel_scale : !INST.pixel_scale
report_plot_include : True
report_table_include : True
    x_size_unit : mm
    y_size_unit : mm


```

10.2.2 DetectorList: "detector_window"

Included by default: True

File Description:

Class Description: A description of detector positions and properties



Changes:

-

id	pixel_size	angle	gain	x_cen	y_cen	x_size	y_size
1	0.015	0.0	1.0	0.0	0.0	15.36	15.36

Data

Meta-data

```

filename : None
name : detector_window
include : True
image_plane_id : 0
temperature : -230
dit : !OBS.dit
ndit : !OBS.ndit
element_name : micado_detector_array
x_cen_unit : mm
y_cen_unit : mm
xhw_unit : mm
yhw_unit : mm
pixsize_unit : mm
angle_unit : deg
gain_unit : electron/adu
z_order : [90, 290, 390, 490]
array_dict : {'id': [1], 'pixsize': [0.015], 'angle': [0.0], 'gain':
pixel_scale : !INST.pixel_scale
active_detectors : all
report_plot_include : True
report_table_include : True
x_size_unit : mm
y_size_unit : mm

```

10.2.3 QuantumEfficiencyCurve: "qe_curve"

Included by default: True

File Description: Quantum efficiency curves for each detector

Class Description: <no docstring>

Changes:

- {datetime.date(2018, 11, 19): '(KL) updated meta data to new format'}
- {datetime.date(2019, 8, 0): '(KL) Added action keyword to meta data'}

Meta-data

```
filename : QE_detector_H2RG.dat
name : qe_curve
image_plane_id : 0
temperature : -230
dit : !OBS.dit
ndit : !OBS.ndit
element_name : micado_detector_array
author : Kieran Leschinski
sources : Finger+ 2008 SPIE
date_created : 2016-01-01
date_modified : 2019-08-09
type : detector:quantum_efficiency
status : Design - guestimated by reading off the graph in Finger+ 200
wavelength_unit : um
action : transmission
z_order : [113, 513]
include : True
ignore_wings : False
wave_min : !SIM.spectral.wave_min
wave_max : !SIM.spectral.wave_max
wave_unit : !SIM.spectral.wave_unit
wave_bin : !SIM.spectral.spectral_resolution
position : -1
```

10.2.4 SummedExposure: "exposure_action"

Included by default: True

File Description: Summing up sky signal for all DITs and NDITs

Class Description: <no docstring>

Changes:

-

Data

Meta-data

```
filename : None
name : exposure_action
image_plane_id : 0
temperature : -230
dit : !OBS.dit
ndit : !OBS.ndit
element_name : micado_detector_array
z_order : [860]
include : True
```

10.2.5 DarkCurrent: "dark_current"

Included by default: True

File Description: MICADO dark current

Class Description: required: dit, ndit, value

Changes:

-

Data

Meta-data

```
filename : None
name : dark_current
image_plane_id : 0
temperature : -230
dit : !OBS.dit
ndit : !OBS.ndit
element_name : micado_detector_array
value : 0.1
z_order : [830]
include : True
```

10.2.6 LinearityCurve: "detector_linearity"

Included by default: True

File Description: Linearity characteristics of H4RG chips

Class Description: <no docstring>

Changes:

- 2018-11-19 (KL) updated meta data to new format
- 2019-08-14 (KL) replaced long 10000000000 with 1e99

Data

Meta-data

```
filename : FPA_linearity.dat
name : detector_linearity
image_plane_id : 0
temperature : -230
dit : !OBS.dit
ndit : !OBS.ndit
element_name : micado_detector_array
author : Kieran Leschinski
sources : Ingraham+ 2014 - Gemini Calibrations II for H2RG
date_created : 2016-01-01
date_modified : 2018-11-19
```



```

        type : detector:linearity
        status : Design - approximated from the H2RG
    incident_unit : ph
    measured_unit : ph
        z_order : [840]
    include : True

```

10.2.7 ShotNoise: "shot_noise"

Included by default: True

File Description: apply poisson shot noise to images

Class Description: <no docstring>

Changes:

-

Data

Meta-data

```

        filename : None
        name : shot_noise
    image_plane_id : 0
        temperature : -230
            dit : !OBS.dit
            ndit : !OBS.ndit
    element_name : micado_detector_array
        z_order : [820]
    include : True
    random_seed : !SIM.random.seed

```

10.2.8 PoorMansHxRGReadoutNoise: "readout_noise"

Included by default: True

File Description: Readout noise frames

Class Description: <no docstring>

Changes:

-

Data

Meta-data

```

        filename : None
        name : readout_noise
    image_plane_id : 0
        temperature : -230
            dit : !OBS.dit

```

```
        ndit : !OBS.ndit
    element_name : micado_detector_array
        noise_std : 12
        n_channels : 64
        z_order : [811]
        include : True
pedestal_fraction : 0.3
    read_fraction : 0.4
    line_fraction : 0.25
channel_fraction : 0.05
    random_seed : !SIM.random.seed
```

11 OpticalElement: "MICADO_simulation_paramters"

Element: simulation

Alias: SIM

Description: RC simulation paramters which need to change for a MICADO run

11.1 Global properties

```
random : {'seed': 9001}
spectral : {'wave_min': 0.7, 'wave_mid': 1.6, 'wave_max': 2.5}
computing : {'preload_field_of_view': True}
reports : {'preamble_file': '../docs/preamble.rst'}
element_name : MICADO_simulation_paramters
```

11.2 Effects

Summary of Effects included in this optical element:

element	name	class	included	z_orders