

ScopeSim instrument packages for MICADO

Doc. No.: ELT-TRE-MCD-56306-0059

Kieran Leschinski, Hugo Buddelmeijer, Oliver Czoske, Miguel Verdugo,
Gijs Verdoes-Kleijn, Werner Zeilinger

September 21, 2020

Contents

1	Introduction	3
1.1	Overview of the Instrument Packages	4
1.1.1	Primary MICADO packages	4
1.1.2	Support packages	4
1.1.3	Adding content to the packages	4
1.2	Contents of packages	5
2	MICADO Pipeline package	6
2.1	Summary of Effects in Optical Elements:	7
2.2	OpticalElement: "MICADO"	8
2.2.1	Global properties	8
2.2.2	Effects	8
2.3	OpticalElement: "MICADO_IMG_LR"	11
2.3.1	Global properties	11
2.3.2	Effects	11
2.4	OpticalElement: "MICADO_IMG_HR"	13
2.4.1	Global properties	13
2.4.2	Effects	13
2.5	OpticalElement: "MICADO_SPEC"	15
2.5.1	Global properties	15
2.5.2	Effects	15
2.6	OpticalElement: "micado_detector_array"	19
2.6.1	Global properties	19
2.6.2	Effects	19
2.7	OpticalElement: "MICADO_simulation_paramters"	27
2.7.1	Global properties	27
2.7.2	Effects	27
3	MICADO Science package	28
4	Supoort packages	29
4.1	OpticalElement: "armazones"	30
4.1.1	Global properties	30
4.1.2	Effects	30
4.2	OpticalElement: "ELT"	34
4.2.1	Global properties	34
4.2.2	Effects	34
4.3	OpticalElement: "MAORY"	37
4.3.1	Global properties	37

4.3.2	Effects	37
4.4	OpticalElement: "default_ro"	40
4.4.1	Global properties	40
4.4.2	Effects	40

Chapter 1

Introduction

1.1 Overview of the Instrument Packages

The MICADO instrument simulator has moved from using the stand alone SimCADO package to using the generic astronomical instrument simulator ScopeSim. As the ScopeSim code is instrument agnostic, all data related to creating instrument models are contained inside instrument packages, which are hosted on the [instrument reference database \(IRDB\)](#).

1.1.1 Primary MICADO packages

This document is primarily concerned with describing the contents of the two major MICADO instrument descriptions: MICADO and MICADO_Sci. These two packages serve two different audiences:

1. The MICADO package contains all information available pertaining to the optical effects expected for the MICADO optical system. The primary user of this package will be the data flow system. The primary use case for this package is the creation of raw data frames for testing the algorithms of the reduction pipelines for the different modes of MICADO. This package is large and therefore computationally expensive and slow.
2. The MICADO_Sci package contains a subset of the effects in the MICADO package. The primary users of this package will be the science team and outside astronomers interested in simulating observations with the future MICADO instrument. The goal of this package is enable observations to be simulated quickly, so that the user can quickly iterate on observation strategies and/or target choices. As such this package contains only the effects which cause the major optical aberrations. It is by nature not complete, but aims to provide a level of detail sufficient for the majority of observation feasibility studies for MICADO

1.1.2 Support packages

The MICADO packages, as the names suggest, only describe the contents of the MICADO instrument. Observations with MICADO will however rely on the ELT infrastructure, which can be decomposed into several parts: Location, Telescope, Relay optics. Each of these additional parts can be considered as closed optical elements in the full observational optical system. Indeed the relay optics element is a replaceable element in the optical path (with MAORY vs stand-alone mode) Hence each of these optical elements have been given their own instrument package, and are referred to as support packages.

The support packages needed to simulate MICADO observations are also described in this document. Specifically these are:

- Armazones
- ELT
- MAORY
- Stand-alone relay optics

For each observation the Armazones and ELT packages are required. However only one of MAORY or the stand-alone relay optics packages are required.

1.1.3 Adding content to the packages

The contents of the packages are currently in the public domain. The raw data is [hosted on Github](#).

Periodically this data is compiled into an instrument package and uploaded to the ScopeSim server. It is these packages which are downloaded by ScopeSim when setting up an observation simulation.

New data or Effect objects can be added by submitting a pull request to the [Github repository](#).

1.2 Contents of packages

Each package contains three types of files:

1. configuration,
2. effect descriptions, and
3. raw data

The configuration files are responsible for controlling which effects and which parameters and values are used when generating the optical model for an observation simulation. The effect files describe which classes and which values should be used when applying an effect to the photon flux of the target object, e.g. which PSF kernel should be applied at which wavelength. The raw data files provide the raw data needed by the Effect objects, e.g. the bitmaps of the PSF kernels.

In the following sections each optical element is described. Each optical element contains a description of all the optical Effects associated with it, as well as a list of the configuration keywords and values required by the effect. If an Effect required data from an external file (e.g. PSF kernels, linearity curves, etc), these data are presented as part of each Effect object - either in the `Table` or `Data` sections.

Note

The raw data will not always be displayed directly.

A representation of the data will be presented where available. For further details the reader is directed to the view the data directly on the [IRDB](#)

Chapter 2

MICADO Pipeline package

2.1 Summary of Effects in Optical Elements:

element	name	class	included	z_orders
armazones	armazones_atmo_default_ter_curve	AtmosphericTERCurve	True	[111, 511]
armazones	armazones_atmo_dispersion	AtmosphericDispersion	True	[231]
armazones	armazones_atmo_skycalc_ter_curve	SkycalcTERCurve	False	[112, 512]
ELT	scope_surface_list	SurfaceList	True	[20, 120, 520]
ELT	scope_vibration	Vibration	True	[244, 744]
ELT	eso_combined_reflection	TERCurve	False	[10, 110, 510]
MICADO	micado_static_surfaces	SurfaceList	True	[20, 120, 520]
MICADO	micado_filter	FilterCurve	True	[114, 214, 514]
MICADO	micado_ncpas_psf	NonCommonPathAberration	True	[241, 641]
micado_detector_array	full_detector_array	DetectorList	False	[90, 290, 390, 490]
micado_detector_array	detector_window	DetectorList	True	[90, 290, 390, 490]
micado_detector_array	qe_curve	QuantumEfficiencyCurve	True	[113, 513]
micado_detector_array	exposure_action	SummedExposure	True	[860]
micado_detector_array	dark_current	DarkCurrent	True	[830]
micado_detector_array	detector_linearity	LinearityCurve	True	[840]
micado_detector_array	shot_noise	ShotNoise	True	[820]
micado_detector_array	readout_noise	PoorMansHxRGReadoutNoise	True	[811]
default_ro	relay_psf	FieldConstantPSF	True	[262, 662]
default_ro	relay_surface_list	SurfaceList	True	[20, 120, 520]
MAORY	maory_surface_list	SurfaceList	True	[20, 120, 520]
MAORY	maory_generic_psf	FieldConstantPSF	True	[262, 662]
MICADO_IMG_LR	micado_wide_field_mirror_list	SurfaceList	True	[20, 120, 520]
MICADO_IMG_LR	micado_adc_3D_shift	AtmosphericDispersionCorrection	True	[632, 232]
MICADO_IMG_HR	zoom_mirror_list	SurfaceList	True	[20, 120, 520]
MICADO_IMG_HR	micado_adc_3D_shift	AtmosphericDispersionCorrection	True	[632, 232]
MICADO_SPEC	spec_mode_optics	SurfaceList	True	[20, 120, 520]
MICADO_SPEC	spectroscopic_slit_aperture	ApertureMask	True	[80, 280, 380]
MICADO_SPEC	micado_spectral_traces	SpectralTraceList	True	[70, 270]
MICADO_SPEC	spec_mode_optics	SurfaceList	True	[20, 120, 520]
MICADO_SPEC	spectroscopic_slit_aperture	ApertureMask	True	[80, 280, 380]
MICADO_SPEC	micado_spectral_traces	SpectralTraceList	True	[70, 270]
MICADO_SPEC	spec_mode_optics	SurfaceList	True	[20, 120, 520]
MICADO_SPEC	spectroscopic_slit_aperture	ApertureMask	True	[80, 280, 380]
MICADO_SPEC	micado_spectral_traces	SpectralTraceList	True	[70, 270]

2.2 OpticalElement: "MICADO"

Element: instrument

Alias: INST

Description: Effects from the MICADO common optics

2.2.1 Global properties

```
temperature : -190
element_name : MICADO
```

2.2.2 Effects

Summary of Effects included in this optical element:

element	name	class	included	z_orders
MICADO	micado_static_surfaces	SurfaceList	True	[20, 120, 520]
MICADO	micado_filter	FilterCurve	True	[114, 214, 514]
MICADO	micado_ncpas_psf	NonCommonPathAberration	True	[241, 641]

2.2.2.1 SurfaceList: "micado_static_surfaces"

Included by default: True

File Description: surfaces list for wide field optics

Class Description: <no docstring>

Changes:

- {datetime.date(2019, 1, 28): '(KL) Changed column names and added units to header'}
- {datetime.date(2019, 7, 10): '(KL) Shortened the list to only the swappable mirrors'}
- {datetime.date(2020, 8, 25): '(KL) Updated angle_unit to degree from degrees (why has astropy not complained until now?)'}

Data

Meta-data

```
filename : LIST_MICADO_mirrors_static.dat
name : micado_static_surfaces
temperature : -190
element_name : MICADO
author : Kieran Leschinski
source : Ric's SPIE 2018 PPT presentation
date_created : 2018-11-19
date_modified : 2019-07-10
status : Design - pre PDR list of all static MICADO surfaces
type : mirror:list
```

```

        outer_unit : m
        inner_unit : m
        angle_unit : degree
    temperature_unit : deg_C
        z_order : [20, 120, 520]
        include : True
    ignore_wings : False
        wave_min : !SIM.spectral.wave_min
        wave_max : !SIM.spectral.wave_max
        wave_unit : !SIM.spectral.wave_unit
        wave_bin : !SIM.spectral.spectral_resolution
    minimum_throughput : !SIM.spectral.minimum_throughput
        etendue : !TEL.etendue

```

2.2.2.2 FilterCurve: "micado_filter"

Included by default: True

File Description: transmission curve for filter

Class Description: Other Parameters

Changes:

-

Data

Meta-data

```

        filename : filters/TC_filter_Spec_HK.dat
        name : micado_filter
    temperature : -190
    element_name : MICADO
        filter_name : !OBS.filter_name
    filename_format : filters/TC_filter_{}.dat
    minimum_throughput : 0.000101
        outer : 0.2
        outer_unit : m
        author : Ric Davies
        source : Ric Davies
    date_created : 2017-11-20
    date_modified : 2017-11-20
        status : Design - pre PDR list of filters
        z_order : [114, 214, 514]
        include : True
    ignore_wings : False
        wave_min : !SIM.spectral.wave_min
        wave_max : !SIM.spectral.wave_max
        wave_unit : !SIM.spectral.wave_unit
        wave_bin : !SIM.spectral.spectral_resolution
        action : transmission

```

```
position : -1
wing_flux_level : None
```

2.2.2.3 NonCommonPathAberration: "micado_ncpas_psf"

Included by default: True

File Description: Effective NCPA induced PSF kernel

Class Description: Needed: pixel_scale

Changes:

- 2018-11-19 (KL) updated meta data to new format

Data

Meta-data

```
filename : INST_MICADO_wavefront_error_budget.dat
name : micado_ncpas_psf
temperature : -190
element_name : MICADO
pixel_scale : 0.004
author : Kieran Leschinski
sources : Ric Davies email
date_created : 2016-11-21
date_modified : 2018-11-19
type : instrument:wavefront_errors_list
status : Idea - based on the WFE budget and emails with Ric
wfe_rms_unit : nm
z_order : [241, 641]
include : True
flux_accuracy : 0.001
sub_pixel_flag : False
convolve_mode : full
wave_key : WAVE0
normalise_kernel : True
kernel_width : None
strehl_drift : 0.02
wave_min : !SIM.spectral.wave_min
wave_max : !SIM.spectral.wave_max
```

2.3 OpticalElement: "MICADO_IMG_LR"

Element: instrument

Alias: INST

Description: additional effects for the wide-field imaging mode

2.3.1 Global properties

```
pixel_scale : 0.004
plate_scale : 0.266666666666
element_name : MICADO_IMG_LR
```

2.3.2 Effects

Summary of Effects included in this optical element:

element	name	class	included	z_orders
MICADO_IMG_LR	micado_wide_field_mirror_list	SurfaceList	True	[20, 120, 520]
MICADO_IMG_LR	micado_adc_3D_shift	AtmosphericDispersionCorrection	True	[632, 232]

2.3.2.1 SurfaceList: "micado_wide_field_mirror_list"

Included by default: True

File Description: list of extra mirrors needed for the wide field mode

Class Description: <no docstring>

Changes:

- {datetime.date(2019, 1, 28): '(KL) Changed column names and added units to header'}
- {datetime.date(2019, 7, 10): '(KL) Shortened the list to only the swappable mirrors'}

Data

Meta-data

```
filename : LIST_MICADO_mirrors_wide.dat
name : micado_wide_field_mirror_list
pixel_scale : 0.004
plate_scale : 0.266666666666
element_name : MICADO_IMG_LR
author : Kieran Leschinski
source : Ric's SPIE 2018 PPT presentation
date_created : 2018-11-19
date_modified : 2019-07-10
status : Design - pre PDR list of MICADO mirrors for wide-field mo
type : mirror:list
outer_unit : m
inner_unit : m
```

```

        angle_unit : degree
    temperature_unit : deg_C
        z_order : [20, 120, 520]
        include : True
    ignore_wings : False
        wave_min : !SIM.spectral.wave_min
        wave_max : !SIM.spectral.wave_max
        wave_unit : !SIM.spectral.wave_unit
        wave_bin : !SIM.spectral.spectral_resolution
    minimum_throughput : !SIM.spectral.minimum_throughput
        etendue : !TEL.etendue

```

2.3.2.2 AtmosphericDispersionCorrection: "micado_adc_3D_shift"

Included by default: True

File Description: atmospheric dispersion corrector

Class Description: <no docstring>

Changes:

-

Data

Meta-data

```

    filename : None
        name : micado_adc_3D_shift
    pixel_scale : 0.004
    plate_scale : 0.266666666666
    element_name : MICADO_IMG_LR
        altitude : !ATMO.altitude
        longitude : !ATMO.longitude
        latitude : !ATMO.latitude
        airmass : !OBS.airmass
    temperature : !ATMO.temperature
        humidity : !ATMO.humidity
        pressure : !ATMO.pressure
    pupil_angle : !OBS.pupil_angle
    efficiency : 1
        wave_mid : !SIM.spectral.wave_mid
    quick_adc : True
        z_order : [632, 232]
        include : True

```

2.4 OpticalElement: "MICADO_IMG_HR"

Element: instrument

Alias: INST

Description: additional effects for the zoom imaging mode

2.4.1 Global properties

```
pixel_scale : 0.0015
plate_scale : 0.1
element_name : MICADO_IMG_HR
```

2.4.2 Effects

Summary of Effects included in this optical element:

element	name	class	included	z_orders
MICADO_IMG_HR	zoom_mirror_list	SurfaceList	True	[20, 120, 520]
MICADO_IMG_HR	micado_adc_3D_shift	AtmosphericDispersionCorrection	True	[632, 232]

2.4.2.1 SurfaceList: "zoom_mirror_list"

Included by default: True

File Description: list of extra mirror needed for the zoom imaging mode

Class Description: <no docstring>

Changes:

- {datetime.date(2019, 1, 28): '(KL) Changed column names and added units to header'}
- {datetime.date(2019, 7, 10): '(KL) Shortened the list to only the swappable mirrors'}

Data

Meta-data

```
filename : LIST_MICADO_mirrors_zoom.dat
name : zoom_mirror_list
pixel_scale : 0.0015
plate_scale : 0.1
element_name : MICADO_IMG_HR
author : Kieran Leschinski
source : Ric's SPIE 2018 PPT presentation
date_created : 2018-11-19
date_modified : 2019-07-10
status : Design - pre PDR list of swappable mirrors for zoom mode
type : mirror:list
ETypes : SURFLIST
EDIM : 1
```

```

        outer_unit : m
        inner_unit : m
        angle_unit : degree
    temperature_unit : deg_C
        z_order : [20, 120, 520]
        include : True
    ignore_wings : False
        wave_min : !SIM.spectral.wave_min
        wave_max : !SIM.spectral.wave_max
        wave_unit : !SIM.spectral.wave_unit
        wave_bin : !SIM.spectral.spectral_resolution
    minimum_throughput : !SIM.spectral.minimum_throughput
        etendue : !TEL.etendue

```

2.4.2.2 AtmosphericDispersionCorrection: "micado_adc_3D_shift"

Included by default: True

File Description: atmospheric dispersion corrector

Class Description: <no docstring>

Changes:

-

Data

Meta-data

```

    filename : None
        name : micado_adc_3D_shift
    pixel_scale : 0.0015
    plate_scale : 0.1
    element_name : MICADO_IMG_HR
        altitude : !ATMO.altitude
        longitude : !ATMO.longitude
        latitude : !ATMO.latitude
        airmass : !OBS.airmass
    temperature : !ATMO.temperature
        humidity : !ATMO.humidity
        pressure : !ATMO.pressure
    pupil_angle : !OBS.pupil_angle
        wave_mid : !SIM.spectral.wave_mid
    efficiency : 1
    quick_adc : True
        z_order : [632, 232]
        include : True

```

2.5 OpticalElement: "MICADO_SPEC"

Element: instrument

Alias: INST

Description: additional effects for the spectroscopy mode

2.5.1 Global properties

```
pixel_scale : 0.004
plate_scale : 0.2666666667
element_name : MICADO_SPEC
```

2.5.2 Effects

Summary of Effects included in this optical element:

element	name	class	included	z_orders
MICADO_SPEC	spec_mode_optics	SurfaceList	True	[20, 120, 520]
MICADO_SPEC	spectroscopic_slit_aperture	ApertureMask	True	[80, 280, 380]
MICADO_SPEC	micado_spectral_traces	SpectralTraceList	True	[70, 270]

2.5.2.1 SurfaceList: "spec_mode_optics"

Included by default: True

File Description: list of extra mirrors needed for the spectroscopy mode

Class Description: <no docstring>

Changes:

- {datetime.date(2019, 1, 28): '(KL) Changed column names and added units to header'}
- {datetime.date(2019, 7, 10): '(KL) Shortened the list to only the swappable gratings'}

Data

Meta-data

```
filename : LIST_MICADO_mirrors_spec.dat
name : spec_mode_optics
pixel_scale : 0.004
plate_scale : 0.2666666667
element_name : MICADO_SPEC
author : Kieran Leschinski
source : Ric's SPIE 2018 PPT presentation
date_created : 2018-11-19
date_modified : 2019-07-10
status : Design - pre PDR list of swappable optics for spectroscopy
type : mirror:list
ETYPE : SURFLIST
```



```

        EDIM : 1
    outer_unit : m
    inner_unit : m
    angle_unit : degree
    temperature_unit : deg_C
        z_order : [20, 120, 520]
    include : True
    ignore_wings : False
        wave_min : !SIM.spectral.wave_min
        wave_max : !SIM.spectral.wave_max
        wave_unit : !SIM.spectral.wave_unit
        wave_bin : !SIM.spectral.spectral_resolution
    minimum_throughput : !SIM.spectral.minimum_throughput
        etendue : !TEL.etendue

```

2.5.2.2 ApertureMask: "spectroscopic_slit_aperture"

Included by default: True

File Description: Slit mask for the short, narrow slit (3 arcsec x 20 mas)

Class Description: Only provides the on-sky window coords of the Aperture

Changes:

- {datetime.date(2019, 7, 10): '(KL) Created the file'}
- {datetime.date(2020, 3, 24): '(KL) Changed geometry to 3000x20mas'}

Data

Meta-data

```

    filename : !OBS.slit_file
        name : spectroscopic_slit_aperture
    pixel_scale : 0.004
    plate_scale : 0.2666666667
    element_name : MICADO_SPEC
        author : Kieran Leschinski
        source : My imagination
    date_created : 2019-07-10
    date_modified : 2019-07-10
        status : Guess - in the train on the way home from CM13
        type : aperture:slit_geometry
    x_unit : arcsec
    y_unit : arcsec
    z_order : [80, 280, 380]
    include : True
    no_mask : True
        angle : 0
        shape : rect
    conserve_image : True
        id : 0

```

```

<SpectralTrace> "list of spectral order trace geometry on the focal plane" : [1.93, 2.46]um : Ext 2 : Aperture
0 : ImagePlane 0 <SpectralTrace> "list of spectral order trace geometry on the focal plane" : [1.45, 1.85]um :
Ext 3 : Aperture 0 : ImagePlane 0 <SpectralTrace> "list of spectral order trace geometry on the focal plane"
: [1.16, 1.48]um : Ext 4 : Aperture 0 : ImagePlane 0 <SpectralTrace> "list of spectral order trace geometry
on the focal plane" : [1.16, 1.39]um : Ext 5 : Aperture 0 : ImagePlane 0 <SpectralTrace> "list of spectral
order trace geometry on the focal plane" : [0.97, 1.23]um : Ext 6 : Aperture 0 : ImagePlane 0 <SpectralTrace>
"list of spectral order trace geometry on the focal plane" : [0.97, 1.23]um : Ext 7 : Aperture 0 : ImagePlane 0
<SpectralTrace> "list of spectral order trace geometry on the focal plane" : [0.83, 1.05]um : Ext 8 : Aperture
0 : ImagePlane 0 <SpectralTrace> "list of spectral order trace geometry on the focal plane" : [0.83, 1.05]um :
Ext 9 : Aperture 0 : ImagePlane 0 <SpectralTrace> "list of spectral order trace geometry on the focal plane"
: [0.83, 0.92]um : Ext 10 : Aperture 0 : ImagePlane 0 <SpectralTrace> "list of spectral order trace geometry
on the focal plane" : [0.73, 0.92]um : Ext 11 : Aperture 0 : ImagePlane 0 <SpectralTrace> "list of spectral
order trace geometry on the focal plane" : [0.73, 0.92]um : Ext 12 : Aperture 0 : ImagePlane 0 <Spectral-
Trace> "list of spectral order trace geometry on the focal plane" : [0.65, 0.82]um : Ext 13 : Aperture 0 :
ImagePlane 0 <SpectralTrace> "list of spectral order trace geometry on the focal plane" : [0.65, 0.82]um : Ext
14 : Aperture 0 : ImagePlane 0 <SpectralTrace> "list of spectral order trace geometry on the focal plane" :
[0.6, 0.74]um : Ext 15 : Aperture 0 : ImagePlane 0 <SpectralTrace> "list of spectral order trace geometry on
the focal plane" : [0.6, 0.73]um : Ext 16 : Aperture 0 : ImagePlane 0 <SpectralTrace> "list of spectral order
trace geometry on the focal plane" : [0.6, 0.67]um : Ext 17 : Aperture 0 : ImagePlane 0 <SpectralTrace>
"list of spectral order trace geometry on the focal plane" : [0.6, 0.67]um : Ext 18 : Aperture 0 : ImagePlane 0
*****

```

Included by default: True

File Description: list of spectral order trace geometry on the focal plane

Class Description: List of spectral trace geometries for the detector plane

Changes:

-

Data

Meta-data

```

filename : !OBS.trace_file
name : micado_spectral_traces
pixel_scale : 0.004
plate_scale : 0.2666666667
element_name : MICADO_SPEC
wave_colname : lam
s_colname : xi
col_number_start : 1
invalid_value : 0
SIMPLE : True
BITPIX : 8
NAXIS : 0
EXTEND : True
FILETYPE : Spectral Layout Definition
AUTHOR : Oliver Czoske
DATE : 2018-09-16
SOURCE : Frank Grupp

```

ORIGDATE : 2018-06-29
STATUS : Design PDR
ECAT : 1
EDATA : 2
DESCRIPT : Maps spectral traces from long slit aperture to detector im
DATE_CRE : 2018-06-29
DATE_MOD : 2019-09-16
HISTORY : 2019-09-16 : (KL) Added aperture-imagePlane table to EXT 1
z_order : [70, 270]
include : True
wave_min : !SIM.spectral.wave_min
wave_max : !SIM.spectral.wave_max
x_colname : x
y_colname : y
dwave : 0.002

2.6 OpticalElement: "micado_detector_array"

Element: detector

Alias: DET

Description: A set of 9 H4RG detectors

2.6.1 Global properties

```
image_plane_id : 0
temperature    : -230
               dit : !OBS.dit
               ndit : !OBS.ndit
element_name   : micado_detector_array
```

2.6.2 Effects

Summary of Effects included in this optical element:

element	name	class	included	z_orders
micado_detector_array	full_detector_array	DetectorList	False	[90, 290, 390, 490]
micado_detector_array	detector_window	DetectorList	True	[90, 290, 390, 490]
micado_detector_array	qe_curve	QuantumEfficiencyCurve	True	[113, 513]
micado_detector_array	exposure_action	SummedExposure	True	[860]
micado_detector_array	dark_current	DarkCurrent	True	[830]
micado_detector_array	detector_linearity	LinearityCurve	True	[840]
micado_detector_array	shot_noise	ShotNoise	True	[820]
micado_detector_array	readout_noise	PoorMansHxRGReadoutNoise	True	[811]

2.6.2.1 DetectorList: "full_detector_array"

Included by default: False

File Description: MICADO detector array list

Class Description: A description of detector positions and properties

Changes:

- {datetime.date(2017, 8, 12): '(OC) id changed to conform with spectroscopy report'}
- {datetime.date(2018, 7, 26): '(OC) large gap (chips 5 and 6) reduced to 8 mm'}
- {datetime.date(2018, 11, 19): '(KL) updated meta data to new format'}
- {datetime.date(2019, 1, 28): '(KL) moved units into header'}

id	x_cen	y_cen	x_size	y_size	x_len	y_len	pixel_size	angle	gain
1	-63.84	63.84	61.44	61.44	4096	4096	0.015	0.0	1.0
2	0.0	63.84	61.44	61.44	4096	4096	0.015	0.0	1.0

... continued on next page

id	x_cen	y_cen	x_size	y_size	x_len	y_len	pixel_size	angle	gain
3	63.84	63.84	61.44	61.44	4096	4096	0.015	0.0	1.0
4	63.84	0.0	61.44	61.44	4096	4096	0.015	0.0	1.0
5	0.0	0.0	61.44	61.44	4096	4096	0.015	0.0	1.0
6	-69.44	0.0	61.44	61.44	4096	4096	0.015	0.0	1.0
7	-63.84	-63.84	61.44	61.44	4096	4096	0.015	0.0	1.0
8	0.0	-63.84	61.44	61.44	4096	4096	0.015	0.0	1.0
9	63.84	-63.84	61.44	61.44	4096	4096	0.015	0.0	1.0

Data

Meta-data

```

        filename : FPA_array_layout.dat
        name : full_detector_array
        include : False
image_plane_id : 0
    temperature : -230
        dit : !OBS.dit
        ndit : !OBS.ndit
    element_name : micado_detector_array
active_detectors : all
        author : Oliver Czoske
    sources : E-MCD-FPA-572089EB.uda, ELT-TRE-MCD-56300-0011
    date_created : 2017-06-28
    date_modified : 2018-07-26
        type : detector:chip_list
    x_cen_unit : mm
    y_cen_unit : mm
    xhw_unit : mm
    yhw_unit : mm
    x_len_unit : pix
    y_len_unit : pix
    pixsize_unit : mm
    angle_unit : deg
    gain_unit : electron/adu
    z_order : [90, 290, 390, 490]
    pixel_scale : !INST.pixel_scale
report_plot_include : True
report_table_include : True
    x_size_unit : mm
    y_size_unit : mm


```


2.6.2.2 DetectorList: "detector_window"

Included by default: True

File Description:

Class Description: A description of detector positions and properties





Changes:

-

id	pixel_size	angle	gain	x_cen	y_cen	x_size	y_size
1	0.015	0.0	1.0	0.0	0.0	15.36	15.36

Data

Meta-data

```

        filename : None
        name : detector_window
        include : True
image_plane_id : 0
    temperature : -230
        dit : !OBS.dit
        ndit : !OBS.ndit
    element_name : micado_detector_array
        x_cen_unit : mm
        y_cen_unit : mm
        xhw_unit : mm
        yhw_unit : mm
    pixsize_unit : mm
        angle_unit : deg
        gain_unit : electron/adu
        z_order : [90, 290, 390, 490]
        array_dict : {'id': [1], 'pixsize': [0.015], 'angle': [0.0], 'gain':
        pixel_scale : !INST.pixel_scale
    active_detectors : all
report_plot_include : True

```

Meta-data

```
filename : QE_detector_H2RG.dat
name : qe_curve
image_plane_id : 0
temperature : -230
dit : !OBS.dit
ndit : !OBS.ndit
element_name : micado_detector_array
author : Kieran Leschinski
sources : Finger+ 2008 SPIE
date_created : 2016-01-01
date_modified : 2019-08-09
type : detector:quantum_efficiency
status : Design - guestimated by reading off the graph in Finger+ 200
wavelength_unit : um
action : transmission
z_order : [113, 513]
include : True
ignore_wings : False
wave_min : !SIM.spectral.wave_min
wave_max : !SIM.spectral.wave_max
wave_unit : !SIM.spectral.wave_unit
wave_bin : !SIM.spectral.spectral_resolution
position : -1
```

2.6.2.4 SummedExposure: "exposure_action"

Included by default: True

File Description: Summing up sky signal for all DITs and NDITs

Class Description: <no docstring>

Changes:

-

Data

Meta-data

```
filename : None
name : exposure_action
image_plane_id : 0
temperature : -230
dit : !OBS.dit
ndit : !OBS.ndit
element_name : micado_detector_array
z_order : [860]
include : True
```


2.6.2.5 DarkCurrent: "dark_current"

Included by default: True

File Description: MICADO dark current

Class Description: required: dit, ndit, value

Changes:

-

Data

Meta-data

```
filename : None
name : dark_current
image_plane_id : 0
temperature : -230
dit : !OBS.dit
ndit : !OBS.ndit
element_name : micado_detector_array
value : 0.1
z_order : [830]
include : True
```

2.6.2.6 LinearityCurve: "detector_linearity"

Included by default: True

File Description: Linearity characteristics of H4RG chips

Class Description: <no docstring>

Changes:

- 2018-11-19 (KL) updated meta data to new format
- 2019-08-14 (KL) replaced long 10000000000 with 1e99

Data

Meta-data

```
filename : FPA_linearity.dat
name : detector_linearity
image_plane_id : 0
temperature : -230
dit : !OBS.dit
ndit : !OBS.ndit
element_name : micado_detector_array
author : Kieran Leschinski
sources : Ingraham+ 2014 - Gemini Calibrations II for H2RG
date_created : 2016-01-01
date_modified : 2018-11-19
```

```

        type : detector:linearity
        status : Design - approximated from the H2RG
    incident_unit : ph
    measured_unit : ph
        z_order : [840]
    include : True

```

2.6.2.7 ShotNoise: "shot_noise"

Included by default: True

File Description: apply poisson shot noise to images

Class Description: <no docstring>

Changes:

-

Data

Meta-data

```

        filename : None
        name : shot_noise
    image_plane_id : 0
        temperature : -230
            dit : !OBS.dit
            ndit : !OBS.ndit
    element_name : micado_detector_array
        z_order : [820]
    include : True
    random_seed : !SIM.random.seed

```

2.6.2.8 PoorMansHxRGReadoutNoise: "readout_noise"

Included by default: True

File Description: Readout noise frames

Class Description: <no docstring>

Changes:

-

Data

Meta-data

```

        filename : None
        name : readout_noise
    image_plane_id : 0
        temperature : -230
            dit : !OBS.dit

```

```
        ndit : !OBS.ndit
    element_name : micado_detector_array
        noise_std : 12
        n_channels : 64
        z_order : [811]
        include : True
pedestal_fraction : 0.3
    read_fraction : 0.4
    line_fraction : 0.25
channel_fraction : 0.05
    random_seed : !SIM.random.seed
```

2.7 OpticalElement: "MICADO_simulation_paramters"

Element: simulation

Alias: SIM

Description: RC simulation paramters which need to change for a MICADO run

2.7.1 Global properties

```
random : {'seed': 9001}
spectral : {'wave_min': 0.7, 'wave_mid': 1.6, 'wave_max': 2.5}
computing : {'preload_field_of_view': True}
reports : {'preamble_file': '../docs/preamble.rst'}
element_name : MICADO_simulation_paramters
```

2.7.2 Effects

Summary of Effects included in this optical element:

element	name	class	included	z_orders

Chapter 3

MICADO Science package

Chapter 4

Supoort packages

4.1 OpticalElement: "armazones"

Element: atmosphere

Alias: ATMO

Description: Atmosphere and location details for Cerro Armazones

4.1.1 Global properties

```
altitude : 3060
longitude : -70.1918
latitude : -24.5899
temperature : 7
humidity : 0.1
pressure : 0.755
pwv : 2.5
airmass : !OBS.airmass
pupil_angle : !OBS.pupil_angle
pixel_scale : !INST.pixel_scale
element_name : armazones
```

4.1.2 Effects

Summary of Effects included in this optical element:

element	name	class	included	z_orders
armazones	armazones_atmo_default_ter_curve	AtmosphericTERCurve	True	[111, 511]
armazones	armazones_atmo_dispersion	AtmosphericDispersion	True	[231]
armazones	armazones_atmo_skycalc_ter_curve	SkycalcTERCurve	False	[112, 512]

4.1.2.1 AtmosphericTERCurve: "armazones_atmo_default_ter_curve"

Included by default: True

File Description: atmospheric emission and transmission

Class Description: <no docstring>

Changes:

- 2019-07-24 (KL) Created file
- 2019-08-09 (KL) Updated values for airmass 1.2, pwv 2.5

Data

Meta-data

```
filename : TER_armazones_default_NIR_IMG.dat
name : armazones_atmo_default_ter_curve
include : True
altitude : 3060
```

```

longitude : -70.1918
latitude  : -24.5899
temperature : 7
humidity  : 0.1
pressure  : 0.755
pwv       : 2.5
airmass   : !OBS.airmass
pupil_angle : !OBS.pupil_angle
pixel_scale : !INST.pixel_scale
element_name : armazones
author    : Kieran Leschinski
source    : skycalc website for standard Armazones conditions
date_created : 2019-07-24
date_modified : 2019-08-09
status    : Design
type      : atmosphere:ter_curve
season    : entire year
time      : entire night
action    : transmission
wavelength_unit : um
emission_unit : ph s-1 m-2 um-1 arcsec-2
z_order    : [111, 511]
ignore_wings : False
wave_min   : !SIM.spectral.wave_min
wave_max   : !SIM.spectral.wave_max
wave_unit  : !SIM.spectral.wave_unit
wave_bin   : !SIM.spectral.spectral_resolution
area       : !TEL.area
area_unit  : m2
position   : 0

```

4.1.2.2 AtmosphericDispersion: "armazones_atmo_dispersion"

Included by default: True

File Description: atmospheric dispersion

Class Description: Used to generate the wavelength bins based on shifts due to the atmosphere

Changes:

-

Data

Meta-data

```

filename : None
name     : armazones_atmo_dispersion
altitude : 3060
longitude : -70.1918
latitude  : -24.5899

```



```

    temperature : 7
    humidity : 0.1
    pressure : 0.755
    pwv : 2.5
    airmass : !OBS.airmass
    pupil_angle : !OBS.pupil_angle
    pixel_scale : !INST.pixel_scale
    element_name : armazones
    z_order : [231]
    include : True
    wave_min : !SIM.spectral.wave_min
    wave_mid : !SIM.spectral.wave_mid
    wave_max : !SIM.spectral.wave_max
    sub_pixel_fraction : !SIM.sub_pixel.fraction
    num_steps : 1000

```

4.1.2.3 SkycalcTERCurve: "armazones_atmo_skycalc_ter_curve"

Included by default: False

File Description: atmospheric spectra pulled from the skycalc server

Class Description: <no docstring>

Changes:

-

Data

Meta-data

```

filename : None
    name : armazones_atmo_skycalc_ter_curve
    include : False
    altitude : 3060
    longitude : -70.1918
    latitude : -24.5899
temperature : 7
    humidity : 0.1
    pressure : 0.755
    pwv : 2.5
    airmass : !OBS.airmass
    pupil_angle : !OBS.pupil_angle
    pixel_scale : !INST.pixel_scale
element_name : armazones
observatory : armazones
    wmin : 699.9999999999999
    wmax : 2499.999999999995
    wunit : um
    wdelta : 0.09999999999999999
    z_order : [112, 512]

```

```
ignore_wings : False
  wave_min : !SIM.spectral.wave_min
  wave_max : !SIM.spectral.wave_max
wave_unit : !SIM.spectral.wave_unit
  wave_bin : !SIM.spectral.spectral_resolution
    action : transmission
    area : !TEL.area
area_unit : m2
position : 0
```

4.2 OpticalElement: "ELT"

Element: telescope

Alias: TEL

Description: The extremely large telescope

4.2.1 Global properties

```
temperature : !ATMO.temperature
element_name : ELT
```

4.2.2 Effects

Summary of Effects included in this optical element:

element	name	class	included	z_orders
ELT	scope_surface_list	SurfaceList	True	[20, 120, 520]
ELT	scope_vibration	Vibration	True	[244, 744]
ELT	eso_combined_reflection	TERCurve	False	[10, 110, 510]

4.2.2.1 SurfaceList: "scope_surface_list"

Included by default: True

File Description: list of ELT surfaces

Class Description: <no docstring>

Changes:

- 2018-11-19 (KL) Added meta data, added Action column
- 2019-01-28 (KL) Fixed YAML format in meta data
- 2020-08-17 (KL) Updated M1 and M4 dimensions according to ESO-253082_4 sect 4.7 "all-glass" diameter
- 2020-08-17 (KL) Pegged temperature to the atmosphere

Data

Meta-data

```
filename : LIST_mirrors_ELt.tbl
name : scope_surface_list
temperature : !ATMO.temperature
element_name : ELT
author : Oliver Czoske, Kieran Leschinski
source : ESO ELT DRM, ESO-253082_4
date_created : 2018-11-19
date_modified : 2020-08-17
status : Design - pre MICADO-FDR mirror list
```

```

        outer_unit : m
        inner_unit : m
        angle_unit : degree
    temperature_unit : deg_C
        notes : ['2020-08-17 (KL) Coatings match those described in ESO-2
        z_order : [20, 120, 520]
        include : True
    ignore_wings : False
        wave_min : !SIM.spectral.wave_min
        wave_max : !SIM.spectral.wave_max
        wave_unit : !SIM.spectral.wave_unit
        wave_bin : !SIM.spectral.spectral_resolution
    minimum_throughput : !SIM.spectral.minimum_throughput
        etendue : !TEL.etendue

```

4.2.2.2 Vibration: "scope_vibration"

Included by default: True

File Description: residual vibration of telescope

Class Description: Creates a wavelength independent kernel image

Changes:

-

Data

Meta-data

```

        filename : None
        name : scope_vibration
    temperature : 7
    element_name : ELT
        fwhm : 0.001
    pixel_scale : 0.004
        z_order : [244, 744]
        include : True
    flux_accuracy : 0.001
    sub_pixel_flag : False
    convolve_mode : full
        wave_key : WAVE0
    normalise_kernel : True
    width_n_fwhms : 4

```

4.2.2.3 TERCurve: "eso_combined_reflection"

Included by default: False

File Description: single combined reflection curve for clean ELT 5 mirror combination

Class Description: Transmission, Emissivity, Reflection Curve

Changes:

- 2019-11-06 (KL) Converted from .xlsx to .dat file, added ScopeSim meta data
- 2020-07-09 (KL) Added inner and outer dimensions to meta, for use with MICADO-Sci
- 2020-08-17 (KL) Added emissivity column according to ESO-253082_4, sect 4.12.2

Data**Meta-data**

```
filename : TER_ELT_system_20190611.dat
name : eso_combined_reflection
include : False
temperature : !ATMO.temperature
element_name : ELT
temperture : !ATMO.temperature
author : R. Holzloehner
source : See ESO-306070 and ESO-293390 for background.
date_created : 2018-09-18
date_modified : 2019-06-11
type : TERCurve
status : design
action : reflection
outer : 37.3
outer_unit : m
inner : 11.1
inner_unit : m
wavelength_unit : um
notes : ['Baseline coatings.', 'Fresh coatings without contamination']
z_order : [10, 110, 510]
ignore_wings : False
wave_min : !SIM.spectral.wave_min
wave_max : !SIM.spectral.wave_max
wave_unit : !SIM.spectral.wave_unit
wave_bin : !SIM.spectral.spectral_resolution
```

4.3 OpticalElement: "MAORY"

Element: relay_optics

Alias: RO

Description: MAORY AO relay module

4.3.1 Global properties

```
temperature : !ATMO.temperature
psf_filename : None
element_name : MAORY
```

4.3.2 Effects

Summary of Effects included in this optical element:

element	name	class	included	z_orders
MAORY	maory_surface_list	SurfaceList	True	[20, 120, 520]
MAORY	maory_generic_psf	FieldConstantPSF	True	[262, 662]

4.3.2.1 SurfaceList: "maory_surface_list"

Included by default: True

File Description: list of surfaces in MAORY

Class Description: <no docstring>

Changes:

- 2018-11-19 (KL) Added meta data, changed Dichr. filename
- 2019-01-28 (KL) Fixed YAML format in meta data
- 2020-06-22 (KL) Obsolete. Use LIST_mirrors_maory_mms.tbl from now on.

Data

Meta-data

```
filename : LIST_mirrors_MCAO_MAORY.tbl
name : maory_surface_list
temperature : !ATMO.temperature
psf_filename : None
element_name : MAORY
author : Kieran Leschinski
source : Ciliegi+ 2018 SPIE, "MAORY for ELT - preliminary design o
date_created : 2018-11-19
date_modified : 2018-11-19
status : Design - pre PDR list of MAORY mirrors
type : mirror:list
outer_unit : m
```

```

        inner_unit : m
        angle_unit : degree
        temperature_unit : deg_C
        z_order : [20, 120, 520]
        include : True
        ignore_wings : False
        wave_min : !SIM.spectral.wave_min
        wave_max : !SIM.spectral.wave_max
        wave_unit : !SIM.spectral.wave_unit
        wave_bin : !SIM.spectral.spectral_resolution
        minimum_throughput : !SIM.spectral.minimum_throughput
        etendue : !TEL.etendue

```

4.3.2.2 FieldConstantPSF: "maory_generic_psf"

Included by default: True

File Description: MAORY field varying MCAO PSF

Class Description: <no docstring>

Changes:

-

Data

Meta-data

```

        filename : PSF_MCAO_ConstPSF_40_18_6.fits
        name : maory_generic_psf
        temperature : 7
        psf_filename : None
        element_name : MAORY
        warning : Default PSF is not Field Varying. See Documentation
        SIMPLE : True
        BITPIX : 8
        NAXIS : 0
        EXTEND : True
        AUTHOR : Kieran Leschinski
        DATE_CRE : 2019-07-30
        DATE_MOD : 2019-07-30
        SOURCE : AnisoCADO
        STATUS : Best guess for a MAORY ConstantPSF with AnisoCADO
        ETYPE : CONSTPSF
        ECAT : -1
        EDATA : 1
        XOFFSET : 0
        YOFFSET : 0
        z_order : [262, 662]
        include : True
        flux_accuracy : 0.001

```

```
sub_pixel_flag : False
convolve_mode : full
    wave_key : WAVE0
normalise_kernel : True
```


4.4 OpticalElement: "default_ro"

Element: relay_optics

Alias: RO

Description: Simple stand-alone relay optics module

4.4.1 Global properties

```
temperature : !ATMO.temperature
psf_filename : None
element_name : default_ro
```

4.4.2 Effects

Summary of Effects included in this optical element:

element	name	class	included	z_orders
default_ro	relay_psf	FieldConstantPSF	True	[262, 662]
default_ro	relay_surface_list	SurfaceList	True	[20, 120, 520]

4.4.2.1 FieldConstantPSF: "relay_psf"

Included by default: True

File Description: SCAO PSF

Class Description: <no docstring>

Changes:

-

Data

Meta-data

```
filename : PSF_SCAO_ConstPSF_0_5off.fits
name : relay_psf
temperature : 7
psf_filename : None
element_name : default_ro
warning : Default PSF is NOT field varying. See documentation.
SIMPLE : True
BITPIX : 8
NAXIS : 0
EXTEND : True
AUTHOR : Kieran Leschinski
DATE_CRE : 2019-07-30
DATE_MOD : 2019-07-30
SOURCE : AnisoCADO
STATUS : Best guess for a standard observations
```

```

        ETYPE : CONSTPSF
        ECAT : -1
        EDATA : 1
        XOFFSET : 0
        YOFFSET : 5
        z_order : [262, 662]
        include : True
    flux_accuracy : 0.001
    sub_pixel_flag : False
    convolve_mode : full
        wave_key : WAVE0
    normalise_kernel : True

```

4.4.2.2 SurfaceList: "relay_surface_list"

Included by default: True

File Description: list of surfaces in the relay optics

Class Description: <no docstring>

Changes:

- 2018-11-19 (KL) Added meta data
- 2019-01-28 (KL) Fixed YAML format in meta data
- 2020-07-18 (KL) Added all 6 mirrors from the CM16 update pdf
- 2020-07-18 (KL) Pegged temperature to atmosphere

Data

Meta-data

```

        filename : LIST_RO_SCAO_mirrors.dat
        name : relay_surface_list
        temperature : !ATMO.temperature
    psf_filename : None
    element_name : default_ro
        author : Oliver Czoske, Kieran Leschinski
        source : P12_RelayOptics_Status_2020-06-23-MICADO-CM16-RO-v2.pdf
    date_created : 2018-11-19
    date_modified : 2020-08-17
        status : Design - pre FDR list of stand-alone SCAO relay optics mi
        type : mirror:list
    outer_unit : m
    inner_unit : m
    angle_unit : degree
    temperature_unit : deg_C
        z_order : [20, 120, 520]
        include : True
    ignore_wings : False
        wave_min : !SIM.spectral.wave_min

```

```
    wave_max : !SIM.spectral.wave_max  
    wave_unit : !SIM.spectral.wave_unit  
    wave_bin : !SIM.spectral.spectral_resolution  
minimum_throughput : !SIM.spectral.minimum_throughput  
    etendue : !TEL.etendue
```