

ELT – MICADO

Phase C

ScopeSim instrument packages for MICADO

ELT-TRE-MCD-56306-0059

Issue: 1.0

Date: 12. April 2021

Prepared:

K. Leschinski, O. Czoske, M. Verdugo

2021-12-04

.....
Name

.....
Date

.....
Signature

Approved:

.....
Name

.....
Date

.....
Signature

Released:

.....
Name

.....
Date

.....
Signature

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 2 of 106
-------------------	---	---

Change record

Issue/Rev.	Date	Section/Parag. affected	Reason/Initiation/Documents/Remarks
0.1	2020-10-15	All	(KL) Layout initialised
0.2	2020-12-04	All	(KL) Added new data, tables, plots to all sections
1.0	2021-04-12	All	(KL) Minor corrections

Contents

1	Introduction	7
1.1	Applicable Documents	8
1.2	Document Scope	9
1.3	Overview of the Instrument Packages relevant to MICADO	10
1.3.1	Primary MICADO packages	10
1.3.2	Support packages	10
1.3.3	Adding content to the packages	10
1.3.4	Contents of packages	11
2	MICADO Pipeline package	12
2.1	Summary of Effects in Optical Elements:	13
2.2	OpticalElement: "MICADO"	14
2.2.1	Global properties	14
2.2.2	Effects	14
2.2.2.1	SurfaceList: "micado_static_surfaces"	14
2.2.2.2	NonCommonPathAberration: "micado_ncpas_psf"	16
2.2.2.3	FilterWheel: "filter_wheel_1"	18
2.2.2.4	FilterWheel: "filter_wheel_2"	19
2.2.2.5	FilterWheel: "pupil_wheel"	21
2.3	OpticalElement: "MICADO_IMG_LR"	23
2.3.1	Global properties	23
2.3.2	Effects	23
2.3.2.1	SurfaceList: "micado_wide_field_mirror_list"	23
2.3.2.2	AtmosphericDispersionCorrection: "micado_adc_3D_shift"	25
2.4	OpticalElement: "MICADO_IMG_HR"	27
2.4.1	Global properties	27
2.4.2	Effects	27
2.4.2.1	SurfaceList: "zoom_mirror_list"	27
2.4.2.2	AtmosphericDispersionCorrection: "micado_adc_3D_shift"	29
2.5	OpticalElement: "MICADO_SPEC"	31
2.5.1	Global properties	31
2.5.2	Effects	31
2.5.2.1	SurfaceList: "spec_mode_optics"	31
2.5.2.2	ApertureMask: "spectroscopic_slit_aperture"	33

Micado Consortium	ScopeSim instrument packages for MICADO	Doc:	ELT-TRE-MCD-56306-0059
		Issue:	1.0
		Date:	12. April 2021
		Page:	4 of 106

2.5.2.3	SpectralTraceList: "micado_spectral_traces" : 17 traces	34
2.6	OpticalElement: "micado_detector_array"	37
2.6.1	Global properties	37
2.6.2	Effects	37
2.6.2.1	DetectorList: "full_detector_array"	37
2.6.2.2	DetectorList: "detector_window"	39
2.6.2.3	QuantumEfficiencyCurve: "qe_curve"	41
2.6.2.4	SummedExposure: "exposure_action"	42
2.6.2.5	DarkCurrent: "dark_current"	43
2.6.2.6	LinearityCurve: "detector_linearity"	43
2.6.2.7	ShotNoise: "shot_noise"	45
2.6.2.8	PoorMansHxRGReadoutNoise: "readout_noise"	45
2.7	OpticalElement: "MICADO_simulation_paramters"	47
2.7.1	Global properties	47
3	MICADO Science package	48
3.1	Summary of Effects in Optical Elements:	49
3.2	OpticalElement: "MICADO_Sci"	50
3.2.1	Global properties	50
3.2.2	Effects	50
3.2.2.1	TERCurve: "micado_common_optics"	50
3.2.2.2	FilterWheel: "filter_wheel"	52
3.3	OpticalElement: "SCAO"	55
3.3.1	Global properties	55
3.4	OpticalElement: "MICADO_SCAO"	56
3.4.1	Global properties	56
3.4.2	Effects	56
3.4.2.1	TERCurve: "scao_relay_optics_ter"	56
3.4.2.2	AnisocadoConstPSF: "scao_const_psf"	58
3.5	OpticalElement: "MICADO_Sci_SCAO_detector_override"	61
3.5.1	Global properties	61
3.6	OpticalElement: "MCAO"	62
3.6.1	Global properties	62
3.7	OpticalElement: "MICADO_MCAO"	63
3.7.1	Global properties	63
3.7.2	Effects	63
3.7.2.1	TERCurve: "maory_mms_ter"	63
3.7.2.2	AnisocadoConstPSF: "maory_const_psf"	65
3.8	OpticalElement: "MICADO_Sci_MCAO_detector_override"	68
3.8.1	Global properties	68
3.9	OpticalElement: "SPEC"	69
3.9.1	Global properties	69
3.10	OpticalElement: "MICADO_SPEC"	70
3.10.1	Global properties	70
3.10.2	Effects	70

Micado Consortium	ScopeSim instrument packages for MICADO	Doc:	ELT-TRE-MCD-56306-0059
		Issue:	1.0
		Date:	12. April 2021
		Page:	5 of 106

3.10.2.1	RectangularApertureMask: "micado_adjustable_slit"	70
3.10.2.2	SpectralTraceList: "spectral_trace_3000x50mas" : 1 traces	71
3.11	OpticalElement: "MICADO_Sci_SPEC_detector_override"	74
3.11.1	Global properties	74
3.12	OpticalElement: "4mas"	75
3.12.1	Global properties	75
3.13	OpticalElement: "1.5mas"	76
3.13.1	Global properties	76
3.14	OpticalElement: "micado_sci_detector"	77
3.14.1	Global properties	77
3.14.2	Effects	77
3.14.2.1	DetectorWindow: "micado_detector_window"	77
3.14.2.2	QuantumEfficiencyCurve: "h4rg_qe_curve"	79
3.14.2.3	SummedExposure: "exposure_action"	80
3.14.2.4	DarkCurrent: "dark_current"	81
3.14.2.5	ShotNoise: "shot_noise"	82
3.14.2.6	LinearityCurve: "h4rg_detector_linearity"	82
3.14.2.7	PoorMansHxRGReadoutNoise: "readout_noise"	84
4	Support packages	85
4.1	OpticalElement: "armazones"	86
4.1.1	Global properties	86
4.1.2	Effects	86
4.1.2.1	AtmosphericTERCurve: "armazones_atmo_default_ter_curve"	86
4.1.2.2	AtmosphericDispersion: "armazones_atmo_dispersion"	88
4.1.2.3	SkycalcTERCurve: "armazones_atmo_skycalc_ter_curve"	90
4.2	OpticalElement: "ELT"	92
4.2.1	Global properties	92
4.2.2	Effects	92
4.2.2.1	SurfaceList: "scope_surface_list"	92
4.2.2.2	Vibration: "scope_vibration"	94
4.2.2.3	TERCurve: "eso_combined_reflection"	95
4.3	OpticalElement: "MAORY"	98
4.3.1	Global properties	98
4.3.2	Effects	98
4.3.2.1	SurfaceList: "maory_surface_list"	98
4.3.2.2	FieldConstantPSF: "maory_generic_psf"	100
4.4	OpticalElement: "default_ro"	103
4.4.1	Global properties	103
4.4.2	Effects	103
4.4.2.1	FieldConstantPSF: "relay_psf"	103
4.4.2.2	SurfaceList: "relay_surface_list"	105

<p>Micado Consortium</p>	<p>ScopeSim instrument packages for MICADO</p>	<p>Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 6 of 106</p>
--------------------------	--	--

Chapter 1

Introduction

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 8 of 106
-------------------	---	---

1.1 Applicable Documents

Nr	Doc. Nr	Doc. Title	Issue	Date
AD 1	ELT-MAN-MCD-56306-0058	SimCADO User Manual	1.0	2021-04-12
AD 2	ELT-TRE-MCD-56306-0060	ScopeSim - A modular astronomical instrument data simulation environment	1.0	2021-04-12
AD 3	ELT-TRE-MCD-56300-0014	MICADO Masks, Stops, and Filters Description	2.9	2020-12-04

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 9 of 106
-------------------	---	---

1.2 Document Scope

This document aims to serve as a reference for the contents of the instrument packages relevant to the implementation of the MICADO instrument simulator using the [ScopeSim](#) package. The information provided here is a snapshot of the FDR release (Dec. 2020) of the these packages. It is possible that changes will made to files contained in the packages. For more up-to-date information, the reader is referred to the [online GitHub repository](#).

This document does not provide an overview of how to use the MICADO packages with [ScopeSim](#). For this the reader should consult the online documentation for [ScopeSim](#) or either of the two accompanying documents AD 1 and AD 2.

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 10 of 106
-------------------	---	--

1.3 Overview of the Instrument Packages relevant to MICADO

The MICADO instrument simulator has moved from using the stand alone SimCADO package to using the generic astronomical instrument simulator ScopeSim. As the ScopeSim code is instrument agnostic, all data related to creating instrument models are contained inside instrument packages, which are hosted on the [instrument reference database \(IRDB\)](#).

1.3.1 Primary MICADO packages

This document is primarily concerned with describing the contents of the two major MICADO instrument descriptions: MICADO and MICADO_Sci. These two packages serve two different audiences:

1. The MICADO package contains all information available pertaining to the optical effects expected for the MICADO optical system. The primary user of this package will be the data flow system. The primary use case for this package is the creation of raw data frames for testing the algorithms of the reduction pipelines for the different modes of MICADO. This package is large and therefore computationally expensive and slow.
2. The MICADO_Sci package contains a subset of the effects in the MICADO package. The primary users of this package will be the science team and outside astronomers interested in simulating observations with the future MICADO instrument. The goal of this package is enable observations to be simulated quickly, so that the user can quickly iterate on observation strategies and/or target choices. As such this package contains only the effects which cause the major optical aberrations. It is by nature not complete, but aims to provide a level of detail sufficient for the majority of observation feasibility studies for MICADO

1.3.2 Support packages

The MICADO packages, as the names suggest, only describe the contents of the MICADO instrument. Observations with MICADO will however rely on the ELT infrastructure, which can be decomposed into several parts: Location, Telescope, Relay optics. Each of these additional parts can be considered as closed optical elements in the full observational optical system. Indeed the relay optics element is a replacable element in the optical path (with MAORY vs stand-alone mode) Hence each of these optical elements have been given their own instrument package, and are referred to as support packages.

The support packages needed to simulate MICADO observations are also described in this document. Specifically these are:

- Armazones
- ELT
- MAORY
- Stand-alone relay optics

For each observation the Armazones and ELT packages are required. However only one of MAORY or the stand-alone relay optics packages are required.

1.3.3 Adding content to the packages

The contents of the packages are currently in the public domain. The raw data is [hosted on Github](#).

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 11 of 106
-------------------	---	--

Periodically this data is compiled into an instrument package and uploaded to the ScopeSim server. It is these packages which are downloaded by ScopeSim when setting up an observation simulation.

New data or Effect objects can be added by submitting a pull request to the [Github repository](#).

1.3.4 Contents of packages

Each package contains three types of files:

1. configuration,
2. effect descriptions, and
3. raw data

The configuration files are responsible for controlling which effects and which parameters and values are used when generating the optical model for an observation simulation. The effect files describe which classes and which values should be used when applying an effect to the photon flux of the target object, e.g. which PSF kernel should be applied at which wavelength. The raw data files provide the raw data needed by the Effect objects, e.g. the bitmaps of the PSF kernels.

In the following sections each optical element is described. Each optical element contains a description of all the optical Effects associated with it, as well as a list of the configuration keywords and values required by the effect. If an Effect required data from an external file (e.g. PSF kernels, linearity curves, etc), these data are presented as part of each Effect object - either in the `Table` or `Data` sections.

Note

The raw data will not always be displayed directly.

A representation of the data will be presented where available. For further details the reader is directed to view the data directly on the [IRDB](#)

Chapter 2

MICADO Pipeline package

Micado Consortium	ScopeSim instrument packages for MICADO	Doc:	ELT-TRE-MCD-56306-0059
		Issue:	1.0
		Date:	12. April 2021
		Page:	13 of 106

2.1 Summary of Effects in Optical Elements:

element	name	class	included	z_orders
armazones	armazones_atmo_default_ter_curve	AtmosphericTERCurve	True	[111, 511]
armazones	armazones_atmo_dispersion	AtmosphericDispersion	False	[231]
armazones	armazones_atmo_skycalc_ter_curve	SkycalcTERCurve	False	[112, 512]
ELT	scope_surface_list	SurfaceList	True	[20, 120, 520]
ELT	scope_vibration	Vibration	True	[244, 744]
ELT	eso_combined_reflection	TERCurve	False	[10, 110, 510]
MICADO	micado_static_surfaces	SurfaceList	True	[20, 120, 520]
MICADO	micado_ncpas_psf	NonCommonPathAberration	True	[241, 641]
MICADO	filter_wheel_1	FilterWheel	True	[124, 224, 524]
MICADO	filter_wheel_2	FilterWheel	True	[124, 224, 524]
MICADO	pupil_wheel	FilterWheel	True	[124, 224, 524]
micado_detector_array	full_detector_array	DetectorList	False	[90, 290, 390, 490]
micado_detector_array	detector_window	DetectorList	True	[90, 290, 390, 490]
micado_detector_array	qe_curve	QuantumEfficiencyCurve	True	[113, 513]
micado_detector_array	exposure_action	SummedExposure	True	[860]
micado_detector_array	dark_current	DarkCurrent	True	[830]
micado_detector_array	detector_linearity	LinearityCurve	True	[840]
micado_detector_array	shot_noise	ShotNoise	True	[820]
micado_detector_array	readout_noise	PoorMansHxRGReadoutNoise	True	[811]
default_ro	relay_psf	FieldConstantPSF	True	[262, 662]
default_ro	relay_surface_list	SurfaceList	True	[20, 120, 520]
MAORY	maory_surface_list	SurfaceList	True	[20, 120, 520]
MAORY	maory_generic_psf	FieldConstantPSF	True	[262, 662]
MICADO_IMG_LR	micado_wide_field_mirror_list	SurfaceList	True	[20, 120, 520]
MICADO_IMG_LR	micado_adc_3D_shift	AtmosphericDispersionCorrection	False	[632, 232]
MICADO_IMG_HR	zoom_mirror_list	SurfaceList	True	[20, 120, 520]
MICADO_IMG_HR	micado_adc_3D_shift	AtmosphericDispersionCorrection	False	[632, 232]
MICADO_SPEC	spec_mode_optics	SurfaceList	True	[20, 120, 520]
MICADO_SPEC	spectroscopic_slit_aperture	ApertureMask	True	[80, 280, 380]
MICADO_SPEC	micado_spectral_traces	SpectralTraceList	True	[70, 270]

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 14 of 106
-------------------	---	--

2.2 OpticalElement: "MICADO"

Element: instrument

Alias: INST

Description: Effects from the MICADO common optics

2.2.1 Global properties

```

temperature : -190
filter_file_format : filters/TC_filter_{\}.dat
element_name : MICADO

```

2.2.2 Effects

Summary of Effects included in this optical element:

element	name	class	included	z_orders
MICADO	micado_static_surfaces	SurfaceList	True	[20, 120, 520]
MICADO	micado_ncpas_psf	NonCommonPathAberration	True	[241, 641]
MICADO	filter_wheel_1	FilterWheel	True	[124, 224, 524]
MICADO	filter_wheel_2	FilterWheel	True	[124, 224, 524]
MICADO	pupil_wheel	FilterWheel	True	[124, 224, 524]

2.2.2.1 SurfaceList: "micado_static_surfaces"


Included by default: True

File Description: surfaces list for wide field optics

Class Description: <no docstring>

Changes:

- 2019-01-28 (KL) Changed column names and added units to header
- 2019-07-10 (KL) Shortened the list to only the swappable mirrors
- 2020-08-25 (KL) Updated angle_unit to degree from degrees (why has astropy not complained until now?)
- 2020-10-10 (KL) Added SCAO pick-off dichroic after CM17 conversation



name	outer	inner	angle	temperature	action	filename
I00_EntrWin	0.5	0.0	0	0	transmission	TER_entrance_window.dat
I09_SCAO_PO	0.5	0.0	45	-190	reflection	TER_SCAO_dichroic.dat
I01_Fold1	0.5	0.0	45	-190	reflection	TER_mirror_gold.dat
I02_Coli1	0.4	0.0	10	-190	reflection	TER_mirror_gold.dat
I03_Coli2	0.2	0.0	10	-190	reflection	TER_mirror_gold.dat
I04_Coli3	0.2	0.0	10	-190	reflection	TER_mirror_gold.dat
I05_Fold2	0.2	0.0	45	-190	reflection	TER_mirror_gold.dat
I07_ADC	0.2	0.0	0	-190	transmission	TER_full_adc.dat
I10_Fold3	0.2	0.0	45	-190	reflection	TER_mirror_gold.dat
I11_ReIm1	0.2	0.0	10	-190	reflection	TER_mirror_gold.dat
I12_ReIm2	0.2	0.0	10	-190	reflection	TER_mirror_gold.dat
I13_ReIm3	0.2	0.0	10	-190	reflection	TER_mirror_gold.dat

Data

Meta-data

```

filename : LIST_MICADO_mirrors_static.dat
name : micado_static_surfaces
temperature : -190
filter_file_format : filters/TC_filter_{\}.dat

```

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 16 of 106
-------------------	---	--

```

element_name : MICADO
author : Kieran Leschinski
source : Ric's SPIE 2018 PPT presentation
date_created : 2018-11-19
date_modified : 2019-07-10
status : Design, pre PDR list of all static MICADO surfaces
type : mirror:list
outer_unit : m
inner_unit : m
angle_unit : degree
temperature_unit : deg_C
z_order : [20, 120, 520]
include : True
ignore_wings : False
wave_min : !SIM.spectral.wave_min
wave_max : !SIM.spectral.wave_max
wave_unit : !SIM.spectral.wave_unit
wave_bin : !SIM.spectral.spectral_resolution
report_plot_include : True
report_table_include : True
minimum_throughput : !SIM.spectral.minimum_throughput
etendue : !TEL.etendue

```

2.2.2.2 NonCommonPathAberration: "micado_ncpas_psf"

Included by default: True


File Description: Effective NCPA induced PSF kernel

Class Description: Needed: pixel_scale

Changes:

- 2018-11-19 (KL) updated meta data to new format

Micado Consortium	ScopeSim instrument packages for MICADO	Doc:	ELT-TRE-MCD-56306-0059
		Issue:	1.0
		Date:	12. April 2021
		Page:	17 of 106



Data

Meta-data

```

        filename : INST_MICADO_wavefront_error_budget.dat
        name      : micado_ncpas_psf
        temperature : -190
filter_file_format : filters/TC_filter_{\}.dat
        element_name : MICADO
        pixel_scale : 0.004
        author      : Kieran Leschinski
        sources     : Ric Davies email
        date_created : 2016-11-21
        date_modified : 2018-11-19
        type        : instrument:wavefront_errors_list
        status      : Idea - based on the WFE budget and emails with Ric
        wfe_rms_unit : nm
        z_order     : [241, 641]
        include     : True
        flux_accuracy : 0.001
        sub_pixel_flag : False
        convolve_mode : full
        wave_key     : WAVE0
        normalise_kernel : True
report_plot_include : True

```

```

report_table_include : False
kernel_width : None
strehl_drift : 0.02
wave_min : !SIM.spectral.wave_min
wave_max : !SIM.spectral.wave_max

```

2.2.2.3 FilterWheel: "filter_wheel_1"


Included by default: True

File Description:

Class Description: Examples

Changes:

-



name	centre	width	blue cutoff	red cutoff
I-long	0.8689	0.1340	0.8019	0.9359
Y	1.0396	0.1550	0.9621	1.1171
J	1.2502	0.1950	1.1527	1.3477
H	1.6395	0.2900	1.4945	1.7845
Ks	2.1500	0.3500	1.9750	2.3250

... continued on next page

Micado Consortium	ScopeSim instrument packages for MICADO	Doc:	ELT-TRE-MCD-56306-0059
		Issue:	1.0
		Date:	12. April 2021
		Page:	19 of 106

name	centre	width	blue cutoff	red cutoff
J-short	1.1902	0.0490	1.1657	1.2147
J-long	1.2702	0.0490	1.2457	1.2947
H-short	1.5830	0.0850	1.5405	1.6255
H-long	1.6937	0.1120	1.6377	1.7497
K-short	2.0602	0.0600	2.0302	2.0902
K-mid	2.1005	0.1000	2.0505	2.1505
Spec_IJ	1.1663	0.6990	0.8168	1.5158
Spec_HK	2.0345	1.0200	1.5245	2.5445
blank	2.7545	2.7000	1.4045	4.1045

Data

Meta-data

```

        filename : None
        name      : filter_wheel_1
        temperature : -190
filter_file_format : filters/TC_filter_{\}.dat
        element_name : MICADO
        filter_names : ['I-long', 'Y', 'J', 'H', 'Ks', 'J-short', 'J-long',
filename_format : !INST.filter_file_format
        current_filter : !OBS.filter_name_fw1
minimum_throughput : 0.000101
        outer      : 0.2
        outer_unit  : m
        z_order     : [124, 224, 524]
        include     : True
        path        :
report_plot_include : True
report_table_include : True
report_table_rounding : 4

```

2.2.2.4 FilterWheel: "filter_wheel_2"


Included by default: True

File Description:

Class Description: Examples

Changes:

•



name	centre	width	blue cutoff	red cutoff
xI1	0.8355	0.0680	0.8015	0.8695
xI2	0.9005	0.0680	0.8665	0.9345
xY1	1.0006	0.0800	0.9606	1.0406
xY2	1.0756	0.0800	1.0356	1.1156
xJ1	1.2009	0.1100	1.1459	1.2559
xJ2	1.3007	0.1000	1.2507	1.3507
xH1	1.5465	0.1600	1.4665	1.6265
xH2	1.7064	0.1600	1.6264	1.7864
xK1	2.0612	0.1600	1.9812	2.1412
xK2	2.2211	0.1600	2.1411	2.3011
blank	2.7545	2.7000	1.4045	4.1045

Data

Meta-data

```
filename : None
name     : filter_wheel_2
```

Micado Consortium	ScopeSim instrument packages for MICADO	Doc:	ELT-TRE-MCD-56306-0059
		Issue:	1.0
		Date:	12. April 2021
		Page:	21 of 106

```

temperature : -190
filter_file_format : filters/TC_filter_{\}.dat
element_name : MICADO
filter_names : ['xI1', 'xI2', 'xY1', 'xY2', 'xJ1', 'xJ2', 'xH1', 'xH2']
filename_format : !INST.filter_file_format
current_filter : !OBS.filter_name_fw2
minimum_throughput : 0.000101
    outer : 0.2
    outer_unit : m
    z_order : [124, 224, 524]
    include : True
    path :
report_plot_include : True
report_table_include : True
report_table_rounding : 4

```

2.2.2.5 FilterWheel: "pupil_wheel"


Included by default: True

File Description:

Class Description: Examples

Changes:

-



Micado Consortium	ScopeSim instrument packages for MICADO	Doc:	ELT-TRE-MCD-56306-0059
		Issue:	1.0
		Date:	12. April 2021
		Page:	22 of 106

name	centre	width	blue cutoff	red cutoff
H-cont	1.5701	0.0220	1.5591	1.5811
FeII	1.6495	0.0210	1.6390	1.6600
H2_1-0S1	2.1289	0.0280	2.1149	2.1429
Br-gamma	2.1734	0.0280	2.1594	2.1874
K-cont	2.2019	0.0270	2.1884	2.2154
K-long	2.3081	0.0440	2.2861	2.3301
He-I	2.0656	0.0270	2.0521	2.0791
Pa-beta	1.2865	0.0170	1.2780	1.2950
ND1	2.7529	0.0000	2.7529	2.7529
ND3	2.7529	0.0000	2.7529	2.7529
blank	2.7545	2.7000	1.4045	4.1045

Data

Meta-data

```

        filename : None
        name : pupil_wheel
        temperature : -190
filter_file_format : filters/TC_filter_{\}.dat
        element_name : MICADO
        filter_names : ['H-cont', 'FeII', 'H2_1-0S1', 'Br-gamma', 'K-cont',
filename_format : !INST.filter_file_format
        current_filter : !OBS.filter_name_pupil
minimum_throughput : 0.000101
        outer : 0.2
        outer_unit : m
        z_order : [124, 224, 524]
        include : True
        path :
report_plot_include : True
report_table_include : True
report_table_rounding : 4

```

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 23 of 106
-------------------	---	--

2.3 OpticalElement: "MICADO_IMG_LR"

Element: instrument

Alias: INST

Description: additional effects for the wide-field imaging mode

2.3.1 Global properties

```
pixel_scale : 0.004
plate_scale : 0.266666666666
element_name : MICADO_IMG_LR
```

2.3.2 Effects

Summary of Effects included in this optical element:

element	name	class	included	z_orders
MICADO_IMG	micado_wide_field_mirror_list	SurfaceList	True	[20, 120, 520]
MICADO_IMG	micado_adc_3D_shift	AtmosphericDispersionCorrection	False	[632, 232]

2.3.2.1 SurfaceList: "micado_wide_field_mirror_list"


Included by default: True

File Description: list of extra mirrors needed for the wide field mode

Class Description: <no docstring>

Changes:

- 2019-01-28 (KL) Changed column names and added units to header
- 2019-07-10 (KL) Shortened the list to only the swappable mirrors



name	outer	inner	angle	temperature	action	filename
I08_SM5	0.2	0.0	0	-190	reflection	TER_mirror_gold.dat
I09_SM6	0.2	0.0	0	-190	reflection	TER_mirror_gold.dat

Data The list of surfaces from the rotating optics wheel that are added to the optical train when observing in the wide field mode

Meta-data

```

filename : LIST_MICADO_mirrors_wide.dat
name : micado_wide_field_mirror_list
pixel_scale : 0.004
plate_scale : 0.266666666666
element_name : MICADO_IMG_LR
author : Kieran Leschinski
source : Ric's SPIE 2018 PPT presentation
date_created : 2018-11-19
date_modified : 2019-07-10
status : Design, pre PDR list of MICADO mirrors for wide-field
type : mirror:list
outer_unit : m
inner_unit : m
angle_unit : degree

```


Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 25 of 106
-------------------	--	--

```

temperature_unit : deg_C
z_order : [20, 120, 520]
include : True
ignore_wings : False
wave_min : !SIM.spectral.wave_min
wave_max : !SIM.spectral.wave_max
wave_unit : !SIM.spectral.wave_unit
wave_bin : !SIM.spectral.spectral_resolution
report_plot_include : True
report_table_include : True
minimum_throughput : !SIM.spectral.minimum_throughput
etendue : !TEL.etendue

```

2.3.2.2 AtmosphericDispersionCorrection: "micado_adc_3D_shift"

Included by default: False

File Description: atmospheric dispersion corrector

Class Description: <no docstring>

Changes:

-

Data

Meta-data

```

filename : None
name : micado_adc_3D_shift
include : False
pixel_scale : 0.004
plate_scale : 0.266666666666
element_name : MICADO_IMG_LR
altitude : !ATMO.altitude
longitude : !ATMO.longitude
latitude : !ATMO.latitude
airmass : !OBS.airmass
temperature : !ATMO.temperature
humidity : !ATMO.humidity
pressure : !ATMO.pressure
pupil_angle : !OBS.pupil_angle
efficiency : 1
wave_mid : !SIM.spectral.wave_mid

```

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 26 of 106
-------------------	--	--

```

        quick_adc : True
        z_order   : [632, 232]
    report_plot_include : True
    report_table_include : False

```

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 27 of 106
-------------------	---	--

2.4 OpticalElement: "MICADO_IMG_HR"

Element: instrument

Alias: INST

Description: additional effects for the zoom imaging mode

2.4.1 Global properties

```
pixel_scale : 0.0015
plate_scale : 0.1
element_name : MICADO_IMG_HR
```

2.4.2 Effects

Summary of Effects included in this optical element:

element	name	class	included	z_orders
MICADO_IMG_HR	zoom_mirror_list	SurfaceList	True	[20, 120, 520]
MICADO_IMG_HR	micado_adc_3D_shift	AtmosphericDispersionCorrection	False	[632, 232]

2.4.2.1 SurfaceList: "zoom_mirror_list"


Included by default: True

File Description: list of extra mirror needed for the zoom imaging mode

Class Description: <no docstring>

Changes:

- 2019-01-28 (KL) Changed column names and added units to header
- 2019-07-10 (KL) Shortened the list to only the swappable mirrors



name	outer	inner	angle	temperature	action	filename
I08_SM1	0.2	0.0	0	-190	reflection	TER_mirror_gold.dat
I09_SM2	0.2	0.0	0	-190	reflection	TER_mirror_gold.dat
I09_SM3	0.2	0.0	0	-190	reflection	TER_mirror_gold.dat
I09_SM4	0.2	0.0	0	-190	reflection	TER_mirror_gold.dat

Data

Meta-data

```

filename : LIST_MICADO_mirrors_zoom.dat
name : zoom_mirror_list
pixel_scale : 0.0015
plate_scale : 0.1
element_name : MICADO_IMG_HR
author : Kieran Leschinski
source : Ric's SPIE 2018 PPT presentation
date_created : 2018-11-19
date_modified : 2019-07-10
status : Design, pre PDR list of swappable mirrors for zoom mod
type : mirror:list
ETypes : SURFLIST
EDIM : 1

```

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 29 of 106
-------------------	---	--

```

outer_unit : m
inner_unit : m
angle_unit : degree
temperature_unit : deg_C
z_order : [20, 120, 520]
include : True
ignore_wings : False
wave_min : !SIM.spectral.wave_min
wave_max : !SIM.spectral.wave_max
wave_unit : !SIM.spectral.wave_unit
wave_bin : !SIM.spectral.spectral_resolution
report_plot_include : True
report_table_include : True
minimum_throughput : !SIM.spectral.minimum_throughput
etendue : !TEL.etendue

```

2.4.2.2 AtmosphericDispersionCorrection: "micado_adc_3D_shift"

Included by default: False

File Description: atmospheric dispersion corrector

Class Description: <no docstring>

Changes:

-

Data

Meta-data

```

filename : None
name : micado_adc_3D_shift
include : False
pixel_scale : 0.0015
plate_scale : 0.1
element_name : MICADO_IMG_HR
altitude : !ATMO.altitude
longitude : !ATMO.longitude
latitude : !ATMO.latitude
airmass : !OBS.airmass
temperature : !ATMO.temperature
humidity : !ATMO.humidity
pressure : !ATMO.pressure

```

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 30 of 106
-------------------	---	--

```

pupil_angle : !OBS.pupil_angle
  wave_mid : !SIM.spectral.wave_mid
  efficiency : 1
  quick_adc : True
  z_order : [632, 232]
report_plot_include : True
report_table_include : False

```

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 31 of 106
-------------------	---	--

2.5 OpticalElement: "MICADO_SPEC"

Element: instrument

Alias: INST

Description: additional effects for the spectroscopy mode

2.5.1 Global properties

```
pixel_scale : 0.004
plate_scale : 0.2666666667
element_name : MICADO_SPEC
```

2.5.2 Effects

Summary of Effects included in this optical element:

element	name	class	included	z_orders
MICADO_SPEC	spec_mode_optics	SurfaceList	True	[20, 120, 520]
MICADO_SPEC	spectroscopic_slit_aperture	ApertureMask	True	[80, 280, 380]
MICADO_SPEC	micado_spectral_traces	SpectralTraceList	True	[70, 270]

2.5.2.1 SurfaceList: "spec_mode_optics"

Included by default: True


File Description: list of extra mirrors needed for the spectroscopy mode

Class Description: <no docstring>

Changes:

- 2019-01-28 (KL) Changed column names and added units to header
- 2019-07-10 (KL) Shortened the list to only the swappable gratings

Micado Consortium	ScopeSim instrument packages for MICADO	Doc:	ELT-TRE-MCD-56306-0059
		Issue:	1.0
		Date:	12. April 2021
		Page:	32 of 106



name	outer	inner	angle	temperature	action	filename
I08_SM7	0.2	0.0	0	-190	reflection	TER_grating.dat
I09_SM8	0.2	0.0	0	-190	reflection	TER_grating.dat

Data

Meta-data

```

filename : LIST_MICADO_mirrors_spec.dat
name : spec_mode_optics
pixel_scale : 0.004
plate_scale : 0.2666666667
element_name : MICADO_SPEC
author : Kieran Leschinski
source : Ric's SPIE 2018 PPT presentation
date_created : 2018-11-19
date_modified : 2019-07-10
status : Design, pre PDR list of swappable optics for spectroscopy
type : mirror:list
ETypes : SURFLIST
EDIM : 1
outer_unit : m
inner_unit : m

```


Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 33 of 106
-------------------	---	--

```

        angle_unit : degree
    temperature_unit : deg_C
        z_order : [20, 120, 520]
        include : True
    ignore_wings : False
        wave_min : !SIM.spectral.wave_min
        wave_max : !SIM.spectral.wave_max
        wave_unit : !SIM.spectral.wave_unit
        wave_bin : !SIM.spectral.spectral_resolution
    report_plot_include : True
    report_table_include : True
        minimum_throughput : !SIM.spectral.minimum_throughput
        etendue : !TEL.etendue

```

2.5.2.2 ApertureMask: "spectroscopic_slit_aperture"

Included by default: True

File Description: Slit mask for the short, wide slit (3 arcsec x 50 mas)

Class Description: Only provides the on-sky window coords of the Aperture

Changes:

- 2019-07-10 (KL) Created the file
- 2020-03-24 (KL) Changed geometry to 3000x50mas

Data

x	y
-1.5000	-0.0250
1.5000	-0.0250
1.5000	0.0250
-1.5000	0.0250

Meta-data

```

        filename : !OBS.slit_file
        name : spectroscopic_slit_aperture
    pixel_scale : 0.004
    plate_scale : 0.2666666667
    element_name : MICADO_SPEC

```

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 34 of 106
-------------------	---	--

```

author : Kieran Leschinski
source : My imagination
date_created : 2019-07-10
date_modified : 2019-07-10
status : Guess - in the train on the way home from CM13
type : aperture:slit_geometry
x_unit : arcsec
y_unit : arcsec
z_order : [80, 280, 380]
include : True
no_mask : True
angle : 0
shape : rect
conserve_image : True
id : 0
report_plot_include : False
report_table_include : True
report_table_rounding : 4

```

2.5.2.3 SpectralTraceList: "micado_spectral_traces" : 17 traces


Included by default: True

File Description: list of spectral order trace geometry on the focal plane

Class Description: List of spectral trace geometries for the detector plane

Changes:

-



Data

Meta-data

```
filename : !OBS.trace_file
name : micado_spectral_traces
pixel_scale : 0.004
```

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 36 of 106
-------------------	--	--

```

plate_scale : 0.2666666667
element_name : MICADO_SPEC
wave_colname : lam
s_colname : xi
col_number_start : 1
invalid_value : 0
SIMPLE : True
BITPIX : 8
NAXIS : 0
EXTEND : True
FILETYPE : Spectral Layout Definition
AUTHOR : Oliver Czoske
DATE : 2018-09-16
SOURCE : Frank Grupp
ORIGDATE : 2018-06-29
STATUS : Design PDR
ECAT : 1
EDATA : 2
DESCRIPT : Maps spectral traces from long slit aperture to detect
DATE_CRE : 2018-06-29
DATE_MOD : 2019-09-16
HISTORY : 2019-09-16 : (KL) Added aperture-imagePlane table to E
z_order : [70, 270]
include : True
wave_min : !SIM.spectral.wave_min
wave_mid : !SIM.spectral.wave_mid
wave_max : !SIM.spectral.wave_max
x_colname : x
y_colname : y
center_on_wave_mid : False
dwave : 0.002
report_plot_include : True
report_table_include : False

```

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 37 of 106
-------------------	---	--

2.6 OpticalElement: "micado_detector_array"

Element: detector

Alias: DET

Description: A set of 9 H4RG detectors

2.6.1 Global properties

```
image_plane_id : 0
  temperature : -230
    dit : !OBS.dit
    ndit : !OBS.ndit
  element_name : micado_detector_array
```

2.6.2 Effects

Summary of Effects included in this optical element:

element	name	class	included	z_orders
micado_detector_array	full_detector_array	DetectorList	False	[90, 290, 390, 490]
micado_detector_array	detector_window	DetectorList	True	[90, 290, 390, 490]
micado_detector_array	qe_curve	QuantumEfficiencyCurve	True	[113, 513]
micado_detector_array	exposure_action	SummedExposure	True	[860]
micado_detector_array	dark_current	DarkCurrent	True	[830]
micado_detector_array	detector_linearity	LinearityCurve	True	[840]
micado_detector_array	shot_noise	ShotNoise	True	[820]
micado_detector_array	readout_noise	PoorMansHxRGReadoutNoise	True	[811]

2.6.2.1 DetectorList: "full_detector_array"

Included by default: False


File Description: MICADO detector array list

Class Description: A description of detector positions and properties

Changes:

- 2017-08-12 (OC) id changed to conform with spectroscopy report
- 2018-07-26 (OC) large gap (chips 5 and 6) reduced to 8 mm
- 2018-11-19 (KL) updated meta data to new format

- 2019-01-28 (KL) moved units into header



id	x_cen	y_cen	x_size	y_size	x_len	y_len	pixel_size	angle	gain
1	-63.84	63.84	61.44	61.44	4096	4096	0.015	0.0	1.0
2	0.0	63.84	61.44	61.44	4096	4096	0.015	0.0	1.0
3	63.84	63.84	61.44	61.44	4096	4096	0.015	0.0	1.0
4	63.84	0.0	61.44	61.44	4096	4096	0.015	0.0	1.0
5	0.0	0.0	61.44	61.44	4096	4096	0.015	0.0	1.0
6	-69.44	0.0	61.44	61.44	4096	4096	0.015	0.0	1.0
7	-63.84	-63.84	61.44	61.44	4096	4096	0.015	0.0	1.0
8	0.0	-63.84	61.44	61.44	4096	4096	0.015	0.0	1.0
9	63.84	-63.84	61.44	61.44	4096	4096	0.015	0.0	1.0

Data

Meta-data

```

filename : FPA_array_layout.dat
name : full_detector_array
include : False
image_plane_id : 0
temperature : -230

```

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 39 of 106
-------------------	---	--

```

        dit : !OBS.dit
        ndit : !OBS.ndit
        element_name : micado_detector_array
    active_detectors : all
        author : Oliver Czoske
        sources : E-MCD-FPA-572089EB.uda, ELT-TRE-MCD-56300-0011
        date_created : 2017-06-28
        date_modified : 2018-07-26
        type : detector:chip_list
        x_cen_unit : mm
        y_cen_unit : mm
        xhw_unit : mm
        yhw_unit : mm
        x_len_unit : pix
        y_len_unit : pix
        pixsize_unit : mm
        angle_unit : deg
        gain_unit : electron/adu
        z_order : [90, 290, 390, 490]
        pixel_scale : !INST.pixel_scale
    report_plot_include : True
    report_table_include : True
        x_size_unit : mm
        y_size_unit : mm

```

2.6.2.2 DetectorList: "detector_window"

Included by default: True


File Description:

Class Description: A description of detector positions and properties

Changes:

-

Micado Consortium	ScopeSim instrument packages for MICADO	Doc:	ELT-TRE-MCD-56306-0059
		Issue:	1.0
		Date:	12. April 2021
		Page:	40 of 106



id	pixel_size	angle	gain	x_cen	y_cen	x_size	y_size
1	0.015	0.0	1.0	0.0	0.0	15.36	15.36

Data

Meta-data

```

filename : None
name : detector_window
include : True
image_plane_id : 0
temperature : -230
dit : !OBS.dit
ndit : !OBS.ndit
element_name : micado_detector_array
x_cen_unit : mm
y_cen_unit : mm
x_size_unit : mm
y_size_unit : mm
pixel_size_unit : mm
angle_unit : deg
gain_unit : electron/adu
z_order : [90, 290, 390, 490]
array_dict : \{'id': [1], 'pixel_size': [0.015], 'angle': [0.0], 'g

```


Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 41 of 106
-------------------	---	--

```

        pixel_scale : !INST.pixel_scale
        active_detectors : all
        report_plot_include : True
        report_table_include : True

```

2.6.2.3 QuantumEfficiencyCurve: "qe_curve"


Included by default: True

File Description: Quantum efficiency curves for each detector

Class Description: <no docstring>

Changes:

- 2018-11-19 (KL) updated meta data to new format
- 2019-08-09 (KL) Added action keyword to meta data



Data

Meta-data

```

filename : QE_detector_H2RG.dat
name : qe_curve

```

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 42 of 106
-------------------	--	--

```

image_plane_id : 0
  temperature : -230
    dit : 60
    ndit : 1
  element_name : micado_detector_array
  author : Kieran Leschinski
  sources : Finger+ 2008 SPIE
  date_created : 2016-01-01
  date_modified : 2019-08-09
    type : detector:quantum_efficiency
    status : Design, guesstimated by reading off the graph in Finger
wavelength_unit : um
  action : transmission
  z_order : [113, 513]
  include : True
  ignore_wings : False
  wave_min : 0.7
  wave_max : 2.5
  wave_unit : um
  wave_bin : 0.0001
report_plot_include : True
report_table_include : False
  position : -1

```

2.6.2.4 SummedExposure: "exposure_action"

Included by default: True

File Description: Summing up sky signal for all DITs and NDITs

Class Description: Simulates a summed stack of `ndit` exposures

Changes:

-

Data

Meta-data

```

filename : None
  name : exposure_action
image_plane_id : 0
  temperature : -230
    dit : !OBS.dit

```

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 43 of 106
-------------------	--	--

```

        ndit : !OBS.ndit
    element_name : micado_detector_array
        z_order : [860]
        include : True

```

2.6.2.5 DarkCurrent: "dark_current"

Included by default: True

File Description: MICADO dark current

Class Description: required: dit, ndit, value

Changes:

-

Data

Meta-data

```

        filename : None
            name : dark_current
image_plane_id : 0
        temperature : -230
            dit : !OBS.dit
            ndit : !OBS.ndit
        element_name : micado_detector_array
            value : 0.1
            z_order : [830]
            include : True

```

2.6.2.6 LinearityCurve: "detector_linearity"

Included by default: True


File Description: Linearity characteristics of H4RG chips

Class Description: <no docstring>

Changes:

- 2018-11-19 (KL) updated meta data to new format
- 2019-08-14 (KL) replaced long 1000000000 with 1e99

Micado Consortium	ScopeSim instrument packages for MICADO	Doc:	ELT-TRE-MCD-56306-0059
		Issue:	1.0
		Date:	12. April 2021
		Page:	44 of 106



Data

Meta-data

```

        filename : FPA_linearity.dat
          name   : detector_linearity
image_plane_id : 0
    temperature : -230
           dit   : !OBS.dit
          ndit   : !OBS.ndit
    element_name : micado_detector_array
          author : Kieran Leschinski
        sources  : Ingraham+ 2014 - Gemini Calibrations II for H2RG
    date_created : 2016-01-01
    date_modified : 2018-11-19
           type   : detector:linearity
          status  : Design, approximated from the H2RG
    incident_unit : ph
    measured_unit : ph
           z_order : [840]
           include : True
    report_plot_include : True
    report_table_include : False

```

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 45 of 106
-------------------	---	--

2.6.2.7 ShotNoise: "shot_noise"

Included by default: True

File Description: apply poisson shot noise to images

Class Description: <no docstring>

Changes:

-

Data

Meta-data

```

filename : None
name : shot_noise
image_plane_id : 0
temperature : -230
dit : !OBS.dit
ndit : !OBS.ndit
element_name : micado_detector_array
z_order : [820]
include : True
random_seed : !SIM.random.seed

```

2.6.2.8 PoorMansHxRGReadoutNoise: "readout_noise"

Included by default: True

File Description: Readout noise frames

Class Description: <no docstring>

Changes:

-

Data

Meta-data

```

filename : None
name : readout_noise
image_plane_id : 0

```

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 46 of 106
-------------------	---	--

```

    temperature : -230
        dit : !OBS.dit
        ndit : !OBS.ndit
    element_name : micado_detector_array
    noise_std : 12
    n_channels : 64
    z_order : [811]
    include : True
pedestal_fraction : 0.3
    read_fraction : 0.4
    line_fraction : 0.25
    channel_fraction : 0.05
    random_seed : !SIM.random.seed
report_plot_include : False
report_table_include : False

```

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 47 of 106
-------------------	---	--

2.7 OpticalElement: "MICADO_simulation_paramters"

Element: simulation

Alias: SIM

Description: RC simulation paramters which need to change for a MICADO run

2.7.1 Global properties

```

random : \{'seed': 9001\}
spectral : \{'wave_min': 0.7, 'wave_mid': 1.6, 'wave_max': 2.5\}
computing : \{'preload_field_of_view': True\}
reports : \{'preamble_file': '../docs/preamble.rst'\}
element_name : MICADO_simulation_paramters

```

Chapter 3

MICADO Science package

Micado Consortium	ScopeSim instrument packages for MICADO	Doc:	ELT-TRE-MCD-56306-0059
		Issue:	1.0
		Date:	12. April 2021
		Page:	49 of 106

3.1 Summary of Effects in Optical Elements:

element	name	class	included	z_orders
MICADO_Sci	micado_common_optics	TERCurve	True	[10, 110, 510]
MICADO_Sci	filter_wheel	FilterWheel	True	[124, 224, 524]
micado_sci_detector	micado_detector_window	DetectorWindow	True	[90, 290, 390, 490]
micado_sci_detector	h4rg_qe_curve	QuantumEfficiencyCurve	True	[113, 513]
micado_sci_detector	exposure_action	SummedExposure	True	[860]
micado_sci_detector	dark_current	DarkCurrent	True	[830]
micado_sci_detector	shot_noise	ShotNoise	True	[820]
micado_sci_detector	h4rg_detector_linearity	LinearityCurve	False	[840]
micado_sci_detector	readout_noise	PoorMansHxRGReadoutNoise	True	[811]
MICADO_SPEC	micado_adjustable_slit	RectangularApertureMask	True	[80, 280, 380]
MICADO_SPEC	spectral_trace_3000x50mas	SpectralTraceList	True	[70, 270]
MICADO_SCAO	scao_relay_optics_ter	TERCurve	True	[10, 110, 510]
MICADO_SCAO	scao_const_psf	AnisocadoConstPSF	True	[42, 652]
MICADO_MCAO	maory_mms_ter	TERCurve	True	[10, 110, 510]
MICADO_MCAO	maory_const_psf	AnisocadoConstPSF	True	[42, 652]

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 50 of 106
-------------------	---	--

3.2 OpticalElement: "MICADO_Sci"

Element: instrument

Alias: INST

Description: base configuration for MICADO

3.2.1 Global properties

```

temperature : -190
filter_file_format : filters/TC_filter_{\}.dat
element_name : MICADO_Sci

```

3.2.2 Effects

Summary of Effects included in this optical element:

element	name	class	included	z_orders [3]
MICADO_Sci	micado_common_optics	TERCurve	True	10 .. 510
MICADO_Sci	filter_wheel	FilterWheel	True	124 .. 524

3.2.2.1 TERCurve: "micado_common_optics"

Included by default: True


File Description: combined transmission for MICADO common optics

Class Description: Transmission, Emissivity, Reflection Curve

Changes:

-

Micado Consortium	ScopeSim instrument packages for MICADO	Doc:	ELT-TRE-MCD-56306-0059
		Issue:	1.0
		Date:	12. April 2021
		Page:	51 of 106



Data

Meta-data

```

filename : TER_MICADO_IMG_common.dat
name : micado_common_optics
temperature : -190
filter_file_format : filters/TC_filter_{\}.dat
element_name : MICADO_Sci
author : Auto-compiled from source
source : LIST_MICADO_mirrors_static.dat
date_created : 2020-08-25
date_modified : 2020-08-25
area : 0.19634954084936207
area_unit : m2
wavelength_unit : um
emission_unit : photlam
z_order : [10, 110, 510]
include : True
ignore_wings : False
wave_min : 0.7
wave_max : 2.5
wave_unit : um
wave_bin : 0.001
report_plot_include : True

```

Micado Consortium	ScopeSim instrument packages for MICADO	Doc:	ELT-TRE-MCD-56306-0059
		Issue:	1.0
		Date:	12. April 2021
		Page:	52 of 106

```
report_table_include : False
```

3.2.2.2 FilterWheel: "filter_wheel"


Included by default: True

File Description:

Class Description: Examples

Changes:

-



name	centre	width	blue cutoff	red cutoff
I-long	0.8689	0.1340	0.8019	0.9359
Y	1.0396	0.1550	0.9621	1.1171
J	1.2502	0.1950	1.1527	1.3477
H	1.6395	0.2900	1.4945	1.7845
Ks	2.1500	0.3500	1.9750	2.3250
J-short	1.1902	0.0490	1.1657	1.2147
J-long	1.2702	0.0490	1.2457	1.2947
H-short	1.5830	0.0850	1.5405	1.6255

... continued on next page

Micado Consortium	ScopeSim instrument packages for MICADO	Doc:	ELT-TRE-MCD-56306-0059
		Issue:	1.0
		Date:	12. April 2021
		Page:	53 of 106

name	centre	width	blue cutoff	red cutoff
H-long	1.6937	0.1120	1.6377	1.7497
K-short	2.0602	0.0600	2.0302	2.0902
K-mid	2.1005	0.1000	2.0505	2.1505
Spec_IJ	1.1663	0.6990	0.8168	1.5158
Spec_HK	2.0345	1.0200	1.5245	2.5445
xI1	0.8355	0.0680	0.8015	0.8695
xI2	0.9005	0.0680	0.8665	0.9345
xY1	1.0006	0.0800	0.9606	1.0406
xY2	1.0756	0.0800	1.0356	1.1156
xJ1	1.2009	0.1100	1.1459	1.2559
xJ2	1.3007	0.1000	1.2507	1.3507
xH1	1.5465	0.1600	1.4665	1.6265
xH2	1.7064	0.1600	1.6264	1.7864
xK1	2.0612	0.1600	1.9812	2.1412
xK2	2.2211	0.1600	2.1411	2.3011
blank	2.7545	2.7000	1.4045	4.1045
H-cont	1.5701	0.0220	1.5591	1.5811
FeII	1.6495	0.0210	1.6390	1.6600
H2_1-OS1	2.1289	0.0280	2.1149	2.1429
Br-gamma	2.1734	0.0280	2.1594	2.1874
K-cont	2.2019	0.0270	2.1884	2.2154
K-long	2.3081	0.0440	2.2861	2.3301
He-I	2.0656	0.0270	2.0521	2.0791
Pa-beta	1.2865	0.0170	1.2780	1.2950
ND1	2.7529	0.0000	2.7529	2.7529
ND3	2.7529	0.0000	2.7529	2.7529

Data

Meta-data

```

filename : None
name : filter_wheel
temperature : -190
filter_file_format : filters/TC_filter_{\}.dat
element_name : MICADO_Sci
filter_names : ['I-long', 'Y', 'J', 'H', 'Ks', 'J-short', 'J-long',
filename_format : !INST.filter_file_format

```

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 54 of 106
-------------------	--	--

```

    current_filter : !INST.filter_name
  minimum_throughput : 0.000101
        outer : 0.2
    outer_unit : m
      z_order : [124, 224, 524]
    include : True
      path :
  report_plot_include : True
  report_table_include : True
  report_table_rounding : 4

```

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 55 of 106
-------------------	---	--

3.3 OpticalElement: "SCAO"

Element: instrument

Alias: INST

Description: SCAO optical system

3.3.1 Global properties

```
element_name : SCAO
```

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 56 of 106
-------------------	---	--

3.4 OpticalElement: "MICADO_SCAO"

Element: instrument

Alias: INST

Description: MICADO SCAO mode effects

3.4.1 Global properties

```
psf : \{'strehl': 0.8, 'wavelength': 'Ks'\}
element_name : MICADO_SCAO
```

3.4.2 Effects

Summary of Effects included in this optical element:

element	name	class	included	z_orders
MICADO_SCAO	scao_relay_optics_ter	TERCurve	True	[10, 110, 510]
MICADO_SCAO	scao_const_psf	AnisocadoConstPSF	True	[42, 652]

3.4.2.1 TERCurve: "scao_relay_optics_ter"

Included by default: True


File Description: Combined TER curve for stand-alone relay optics module

Class Description: Transmission, Emissivity, Reflection Curve

Changes:

-

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 57 of 106
-------------------	---	--



Data

Meta-data

```

filename : TER_MICADO_RO.dat
name : scao_relay_optics_ter
psf : \{'strehl': 0.8, 'wavelength': 'Ks'\}
element_name : MICADO_SCAO
author : Auto-compiled from source
source : LIST_RO_SCAO_mirrors.dat
date_created : 2020-08-25
date_modified : 2020-08-25
area : 0.22061834409834324
area_unit : m2
wavelength_unit : um
emission_unit : photlam
z_order : [10, 110, 510]
include : True
ignore_wings : False
wave_min : 0.7
wave_max : 2.5
wave_unit : um
wave_bin : 0.001
report_plot_include : True
report_table_include : False

```

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 58 of 106
-------------------	--	--

3.4.2.2 AnisocadoConstPSF: "scao_const_psf"

Included by default: True


File Description: field constant PSF as produced by stand-alone SCAO

Class Description: Makes a SCAO on-axis PSF with a desired Strehl ratio at a given wavelength

Changes:

-

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 59 of 106
-------------------	---	--



Data

Meta-data

```
filename : MICADO_AnisoCADO_rms_map.fits
name : scao_const_psf
psf : \{'strehl': 0.8, 'wavelength': 'Ks'\}
```

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 60 of 106
-------------------	--	--

```

element_name : MICADO_SCAO
  strehl      : !INST.psf.strehl
  wavelength  : !INST.psf.wavelength
psf_side_length : 256
  offset      : [0, 0]
rounded_edges  : True
convolve_mode  : full
  SIMPLE      : True
  BITPIX      : -64
  NAXIS       : 2
  NAXIS1      : 35
  NAXIS2      : 9
  EXTEND      : True
  CRVAL1      : 0
  CRVAL2      : 0.8
  CRPIX1      : 1.0
  CRPIX2      : 1.0
  CDELT1      : 20
  CDELT2      : 0.2
  CUNIT1      : nm
  CUNIT2      : um
  CTYPE1      : LINEAR
  CTYPE2      : LINEAR
  LABEL1      : nmRMS
  LABEL2      : wavelength
  AUTHOR      : Kieran Leschinski
DATE_CRE      : 2019-07-30
DATE_MOD      : 2019-07-30
SOURCE        : AnisoCADO
STATUS        : Strehl as a function of wavelength and wavefront error
  ETYPE       : SRMAP
  ECAT        : -1
  EDATA       : 0
XOFFSET       : 0
YOFFSET       : 0
z_order       : [42, 652]
include       : True
flux_accuracy : 0.001
sub_pixel_flag : False
wave_key      : WAVE0
normalise_kernel : True
report_plot_include : True
report_table_include : False

```

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 61 of 106
-------------------	--	--

3.5 OpticalElement: "MICADO_Sci_SCAO_detector_override"

Element: detector

Alias: DET

Description: A settable window on the detector plane

3.5.1 Global properties

```
width : 1024
height : 1024
element_name : MICADO_Sci_SCAO_detector_override
```

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 62 of 106
-------------------	---	--

3.6 OpticalElement: "MCAO"

Element: instrument

Alias: INST

Description: MCAO optical system

3.6.1 Global properties

```
element_name : MCAO
```

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 63 of 106
-------------------	---	--

3.7 OpticalElement: "MICADO_MCAO"

Element: instrument

Alias: INST

Description: MICADO MCAO mode effects

3.7.1 Global properties

```
psf : \{'strehl': 0.4, 'wavelength': 'Ks'\}
element_name : MICADO_MCAO
```

3.7.2 Effects

Summary of Effects included in this optical element:

element	name	class	included	z_orders
MICADO_MCAO	maory_mms_ter	TERCurve	True	[10, 110, 510]
MICADO_MCAO	maory_const_psf	AnisocadoConstPSF	True	[42, 652]

3.7.2.1 TERCurve: "maory_mms_ter"

Included by default: True


File Description: Combined TER curve for MAORY MMS relay optics module

Class Description: Transmission, Emissivity, Reflection Curve

Changes:

-

Micado Consortium	ScopeSim instrument packages for MICADO	Doc:	ELT-TRE-MCD-56306-0059
		Issue:	1.0
		Date:	12. April 2021
		Page:	64 of 106



Data

Meta-data

```

filename : TER_MAORY_MMS.dat
name : maory_mms_ter
psf : \{'strehl': 0.4, 'wavelength': 'Ks'\}
element_name : MICADO_MCAO
author : Auto-compiled from source
source : LIST_mirrors_maory_mms.tbl
date_created : 2020-08-25
date_modified : 2020-08-25
area : 0.9503317777109126
area_unit : m2
wavelength_unit : um
emission_unit : photlam
z_order : [10, 110, 510]
include : True
ignore_wings : False
wave_min : 0.7
wave_max : 2.5
wave_unit : um
wave_bin : 0.001
report_plot_include : True
report_table_include : False

```


Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 65 of 106
-------------------	--	--

3.7.2.2 AnisocadoConstPSF: "maory_const_psf"

Included by default: True


File Description: field constant PSF as produced by MAORY

Class Description: Makes a SCAO on-axis PSF with a desired Strehl ratio at a given wavelength

Changes:

-

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 66 of 106
-------------------	---	--



Data

Meta-data

```

filename : MICADO_AnisoCADO_rms_map.fits
name      : maory_const_psf
psf       : \{'strehl': 0.4, 'wavelength': 'Ks'\}

```

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 67 of 106
-------------------	--	--

```

element_name : MICADO_MCAO
  strehl      : !INST.psf.strehl
  wavelength  : !INST.psf.wavelength
psf_side_length : 256
  offset      : [0, 0]
rounded_edges  : True
convolve_mode  : full
  SIMPLE      : True
  BITPIX      : -64
  NAXIS       : 2
  NAXIS1      : 35
  NAXIS2      : 9
  EXTEND      : True
  CRVAL1      : 0
  CRVAL2      : 0.8
  CRPIX1      : 1.0
  CRPIX2      : 1.0
  CDELTA1     : 20
  CDELTA2     : 0.2
  CUNIT1      : nm
  CUNIT2      : um
  CTYPE1      : LINEAR
  CTYPE2      : LINEAR
  LABEL1      : nmRMS
  LABEL2      : wavelength
  AUTHOR      : Kieran Leschinski
DATE_CRE      : 2019-07-30
DATE_MOD      : 2019-07-30
SOURCE        : AnisoCADO
STATUS        : Strehl as a function of wavelength and wavefront error
  ETYPE       : SRMAP
  ECAT        : -1
  EDATA       : 0
XOFFSET       : 0
YOFFSET       : 0
z_order       : [42, 652]
include       : True
flux_accuracy : 0.001
sub_pixel_flag : False
wave_key      : WAVE0
normalise_kernel : True
report_plot_include : True
report_table_include : False

```

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 68 of 106
-------------------	--	--

3.8 OpticalElement: "MICADO_Sci_MCAO_detector_override"

Element: detector

Alias: DET

Description: A settable window on the detector plane

3.8.1 Global properties

```
width : 4096
height : 4096
element_name : MICADO_Sci_MCAO_detector_override
```

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 69 of 106
-------------------	---	--

3.9 OpticalElement: "SPEC"

Element: instrument

Alias: INST

Description: Spectroscopy

3.9.1 Global properties

```

filter_name : Spec_HK
pixel_scale : 0.004
plate_scale : 0.266666666666
element_name : SPEC

```

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 70 of 106
-------------------	---	--

3.10 OpticalElement: "MICADO_SPEC"

Element: instrument

Alias: INST

Description: MICADO SPEC mode effects

3.10.1 Global properties

```
psf : \{'wavelength': '!INST.filter_name', 'strehl': 0.4\}
aperture : \{'x': 0, 'y': 0, 'width': 3, 'height': 0.05\}
element_name : MICADO_SPEC
```

3.10.2 Effects

Summary of Effects included in this optical element:

element	name	class	included	z_orders
MICADO_SPEC	micado_adjustable_slit	RectangularApertureMask	True	[80, 280, 380]
MICADO_SPEC	spectral_trace_3000x50mas	SpectralTraceList	True	[70, 270]

3.10.2.1 RectangularApertureMask: "micado_adjustable_slit"

Included by default: True

File Description:

Class Description: <no docstring>

Changes:

-

Data

x	y
-1.5000	-0.0250
1.5000	-0.0250
1.5000	0.0250
-1.5000	0.0250

Meta-data

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 71 of 106
-------------------	--	--

```

        filename : None
            name : micado_adjustable_slit
            psf : \{'wavelength': 'Ks', 'strehl': 0.4\}
        aperture : \{'x': 0, 'y': 0, 'width': 3, 'height': 0.05\}
    element_name : MICADO_SPEC
        width : !INST.aperture.width
        height : !INST.aperture.height
        x : !INST.aperture.x
        y : !INST.aperture.y
    z_order : [80, 280, 380]
    include : True
    pixel_scale : !INST.pixel_scale
    no_mask : True
    angle : 0
    shape : rect
    conserve_image : True
    id : 0
    report_plot_include : False
    report_table_include : True
    report_table_rounding : 4
        x_unit : arcsec
        y_unit : arcsec

```

3.10.2.2 SpectralTraceList: "spectral_trace_3000x50mas" : 1 traces

Included by default: True


File Description:

Class Description: List of spectral trace geometries for the detector plane

Changes:

-

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 72 of 106
-------------------	--	--



Data

Meta-data

```

filename : TRACE_SCI_3arcsec.fits
name : spectral_trace_3000x50mas
psf : \{'wavelength': 'Ks', 'strehl': 0.4\}

```


Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 73 of 106
-------------------	---	--

```

        aperture : \{'x': 0, 'y': 0, 'width': 3, 'height': 0.05\}
    element_name : MICADO_SPEC
center_on_wave_mid : True
        SIMPLE : True
        BITPIX : 8
        NAXIS : 0
        EXTEND : True
        ECAT : 1
        EDATA : 2
        z_order : [70, 270]
        include : True
    pixel_scale : !INST.pixel_scale
    plate_scale : !INST.plate_scale
        wave_min : !SIM.spectral.wave_min
        wave_mid : !SIM.spectral.wave_mid
        wave_max : !SIM.spectral.wave_max
    x_colname : x
    y_colname : y
    s_colname : s
    wave_colname : wavelength
    col_number_start : 0
        dwave : 0.002
    invalid_value : None
    report_plot_include : True
    report_table_include : False

```

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 74 of 106
-------------------	--	--

3.11 OpticalElement: "MICADO_Sci_SPEC_detector_override"

Element: detector

Alias: DET

Description: A settable window on the detector plane

3.11.1 Global properties

```
width : 800
height : 1024
element_name : MICADO_Sci_SPEC_detector_override
```

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 75 of 106
-------------------	---	--

3.12 OpticalElement: "4mas"

Element: instrument

Alias: INST

Description: wide-field imager : 4mas/pix

3.12.1 Global properties

```

filter_name : Ks
pixel_scale : 0.004
plate_scale : 0.266666666666
element_name : 4mas

```

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 76 of 106
-------------------	---	--

3.13 OpticalElement: "1.5mas"

Element: instrument

Alias: INST

Description: zoom imager : 1.5mas/pix

3.13.1 Global properties

```

filter_name : Ks
pixel_scale : 0.0015
plate_scale : 0.1
element_name : 1.5mas

```

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 77 of 106
-------------------	---	--

3.14 OpticalElement: "micado_sci_detector"

Element: detector

Alias: DET

Description: List of MICADO detector effects relevant for astronomers

3.14.1 Global properties

```
image_plane_id : 0
  temperature : -230
    dit : !OBS.dit
    ndit : !OBS.ndit
  width : 4096
  height : 4096
    x : 0
    y : 0
  element_name : micado_sci_detector
```

3.14.2 Effects

Summary of Effects included in this optical element:

element	name	class	included	z_orders
micado_sci_detector	micado_detector_window	DetectorWindow	True	[90, 290, 390, 490]
micado_sci_detector	h4rg_qe_curve	QuantumEfficiencyCurve	True	[113, 513]
micado_sci_detector	exposure_action	SummedExposure	True	[860]
micado_sci_detector	dark_current	DarkCurrent	True	[830]
micado_sci_detector	shot_noise	ShotNoise	True	[820]
micado_sci_detector	h4rg_detector_linearity	LinearityCurve	False	[840]
micado_sci_detector	readout_noise	PoorMansHxRGReadoutNoise	True	[811]

3.14.2.1 DetectorWindow: "micado_detector_window"

Included by default: True


File Description:

Class Description: For when a full DetectorList is too cumbersome

Changes:

-

Micado Consortium	ScopeSim instrument packages for MICADO	Doc:	ELT-TRE-MCD-56306-0059
		Issue:	1.0
		Date:	12. April 2021
		Page:	78 of 106



id	x_cen	y_cen	x_size	y_size	angle	gain	pixel_size
0	!DET.x	!DET.y	!DET.width	!DET.height	0	1	0.015

Data

Meta-data

```

filename : None
name : micado_detector_window
orig_units : pixel
x_cen_unit : pixel
y_cen_unit : pixel
x_size_unit : pixel
y_size_unit : pixel
pixel_size_unit : mm
angle_unit : deg
gain_unit : electron/adu
image_plane_id : 0
temperature : -230
dit : !OBS.dit
ndit : !OBS.ndit
element_name : micado_sci_detector
z_order : [90, 290, 390, 490]
include : True

```

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 79 of 106
-------------------	---	--

```

        pixel_scale : !INST.pixel_scale
        active_detectors : all
        report_plot_include : True
        report_table_include : True

```

3.14.2.2 QuantumEfficiencyCurve: "h4rg_qe_curve"


Included by default: True

File Description: Quantum efficiency curves for each detector

Class Description: <no docstring>

Changes:

- 2018-11-19 (KL) updated meta data to new format
- 2019-08-09 (KL) Added action keyword to meta data



Data

Meta-data

```

filename : QE_detector_H2RG.dat
name : h4rg_qe_curve

```

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 80 of 106
-------------------	---	--

```

image_plane_id : 0
  temperature : -230
    dit : 60
    ndit : 1
    width : 4096
    height : 4096
    x : 0
    y : 0
  element_name : micado_sci_detector
  author : Kieran Leschinski
  sources : Finger+ 2008 SPIE
  date_created : 2016-01-01
  date_modified : 2019-08-09
    type : detector:quantum_efficiency
    status : Design, guestimated by reading off the graph in Finger
wavelength_unit : um
  action : transmission
  z_order : [113, 513]
  include : True
  ignore_wings : False
  wave_min : 0.7
  wave_max : 2.5
  wave_unit : um
  wave_bin : 0.001
report_plot_include : True
report_table_include : False
position : -1

```

3.14.2.3 SummedExposure: "exposure_action"

Included by default: True

File Description: Summing up sky signal for all DITs and NDITs

Class Description: Simulates a summed stack of ndit exposures

Changes:

-

Data

Meta-data

```
filename : None
```


Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 81 of 106
-------------------	--	--

```

        name : exposure_action
image_plane_id : 0
    temperature : -230
        dit : !OBS.dit
        ndit : !OBS.ndit
    width : 4096
    height : 4096
        x : 0
        y : 0
    element_name : micado_sci_detector
    z_order : [860]
    include : True

```

3.14.2.4 DarkCurrent: "dark_current"

Included by default: True

File Description: MICADO dark current

Class Description: required: dit, ndit, value

Changes:

-

Data

Meta-data

```

        filename : None
        name : dark_current
image_plane_id : 0
    temperature : -230
        dit : !OBS.dit
        ndit : !OBS.ndit
    width : 4096
    height : 4096
        x : 0
        y : 0
    element_name : micado_sci_detector
    value : 0.1
    z_order : [830]
    include : True

```

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 82 of 106
-------------------	---	--

3.14.2.5 ShotNoise: "shot_noise"

Included by default: `True`

File Description: apply poisson shot noise to images

Class Description: <no docstring>

Changes:

-

Data

Meta-data

```

filename : None
name : shot_noise
image_plane_id : 0
temperature : -230
dit : !OBS.dit
ndit : !OBS.ndit
width : 4096
height : 4096
x : 0
y : 0
element_name : micado_sci_detector
z_order : [820]
include : True
random_seed : !SIM.random.seed

```

3.14.2.6 LinearityCurve: "h4rg_detector_linearity"

Included by default: `False`


File Description: Linearity characteristics of H4RG chips

Class Description: <no docstring>

Changes:

- 2018-11-19 (KL) updated meta data to new format
- 2019-08-14 (KL) replaced long 1000000000 with 1e99

Micado Consortium	ScopeSim instrument packages for MICADO	Doc:	ELT-TRE-MCD-56306-0059
		Issue:	1.0
		Date:	12. April 2021
		Page:	83 of 106



Data

Meta-data

```

filename : FPA_linearity.dat
name : h4rg_detector_linearity
include : False
image_plane_id : 0
temperature : -230
dit : !OBS.dit
ndit : !OBS.ndit
width : 4096
height : 4096
x : 0
y : 0
element_name : micado_sci_detector
author : Kieran Leschinski
sources : Ingraham+ 2014 - Gemini Calibrations II for H2RG
date_created : 2016-01-01
date_modified : 2018-11-19
type : detector:linearity
status : Design, approximated from the H2RG
incident_unit : ph
measured_unit : ph
z_order : [840]
```

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 84 of 106
-------------------	--	--

```
report_plot_include : True
report_table_include : False
```

3.14.2.7 PoorMansHxRGReadoutNoise: "readout_noise"

Included by default: True

File Description: Readout noise frames

Class Description: <no docstring>

Changes:

-

Data

Meta-data

```
filename : None
name : readout_noise
image_plane_id : 0
temperature : -230
dit : !OBS.dit
ndit : !OBS.ndit
width : 4096
height : 4096
x : 0
y : 0
element_name : micado_sci_detector
noise_std : 12
n_channels : 64
z_order : [811]
include : True
pedestal_fraction : 0.3
read_fraction : 0.4
line_fraction : 0.25
channel_fraction : 0.05
random_seed : !SIM.random.seed
report_plot_include : False
report_table_include : False
```

Chapter 4

Support packages

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 86 of 106
-------------------	---	--

4.1 OpticalElement: "armazones"

Element: atmosphere

Alias: ATMO

Description: Atmosphere and location details for Cerro Armazones

4.1.1 Global properties

```

altitude : 3060
longitude : -70.1918
latitude : -24.5899
temperature : 7
humidity : 0.1
pressure : 0.755
pwv : 2.5
airmass : !OBS.airmass
pupil_angle : !OBS.pupil_angle
pixel_scale : !INST.pixel_scale
background : \{'filter_name': 'Ks', 'value': 13.6, 'unit': 'mag'\}
spectrum : \{'filename': 'TER_armazones_default_FULL_IMG.dat'\}
element_name : armazones

```

4.1.2 Effects

Summary of Effects included in this optical element:

element	name	class	included	z_orders
armazones	armazones_atmo_default_ter_curve	AtmosphericTERCurve	True	[111, 511]
armazones	armazones_atmo_dispersion	AtmosphericDispersion	False	[231]
armazones	armazones_atmo_skycalc_ter_curve	SkycalcTERCurve	False	[112, 512]

4.1.2.1 AtmosphericTERCurve: "armazones_atmo_default_ter_curve"

Included by default: True


File Description: atmospheric emission and transmission

Class Description: <no docstring>

Changes:

- 2020-10-29 (MV) Created file

Micado Consortium	ScopeSim instrument packages for MICADO	Doc:	ELT-TRE-MCD-56306-0059
		Issue:	1.0
		Date:	12. April 2021
		Page:	87 of 106



Data

Meta-data

filename	: TER_armazones_default_FULL_IMG.dat
name	: armazones_atmo_default_ter_curve
include	: True
altitude	: 3060
longitude	: -70.1918
latitude	: -24.5899
temperature	: 7
humidity	: 0.1
pressure	: 0.755
pwv	: 2.5
airmass	: 1.2
pupil_angle	: 0
pixel_scale	: 0.004
background	: \{'filter_name': 'Ks', 'value': 13.6, 'unit': 'mag'\}
spectrum	: \{'filename': 'TER_armazones_default_FULL_IMG.dat'\}
element_name	: armazones
area	: 0
rescale_emission	: \{'filter_name': 'Ks', 'filename_format': 'filters/TC_
author	: Miguel Verdugo
source	: skycalc_ipy tool for standard Armazones conditions
date_created	: 2020-10-29

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 88 of 106
-------------------	---	--

```

date_modified : 2020-10-29
status : Design
type : atmosphere:ter_curve
wdelta : 10
wmin : 300
wmax : 15000
season : entire year
time : entire night
action : transmission
wavelength_unit : um
emission_unit : ph s-1 m-2 um-1 arcsec-2
z_order : [111, 511]
ignore_wings : False
wave_min : 0.7
wave_max : 2.5
wave_unit : um
wave_bin : 0.0001
report_plot_include : True
report_table_include : False
position : 0

```

4.1.2.2 AtmosphericDispersion: "armazones_atmo_dispersion"

Included by default: False


File Description: atmospheric dispersion

Class Description: Used to generate the wavelength bins based on shifts due to the atmosphere

Changes:

-

Micado Consortium	ScopeSim instrument packages for MICADO	Doc:	ELT-TRE-MCD-56306-0059
		Issue:	1.0
		Date:	12. April 2021
		Page:	89 of 106



Data

Meta-data

```

filename : None
  name   : armazones_atmo_dispersion
include  : False
altitude : 3060
longitude : -70.1918
latitude : -24.5899
temperature : 7
humidity   : 0.1
pressure  : 0.755
  pwv     : 2.5
  airmass : 1.2
pupil_angle : 0
pixel_scale : 0.004
background : \{'filter_name': 'Ks', 'value': 13.6, 'unit': 'mag'\}
spectrum   : \{'filename': 'TER_armazones_default_FULL_IMG.dat'\}
element_name : armazones
  z_order   : [231]
report_plot_include : True
report_table_include : False
  wave_min  : 0.7
  wave_mid  : 1.6

```

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 90 of 106
-------------------	---	--

```

        wave_max : 2.5
sub_pixel_fraction : 1
        num_steps : 1000
           z0 : 33.55730976192071
           temp : 7
        rel_hum : 10.0
           pres : 755.0
           lat : -24.5899
           h : 3060

```

4.1.2.3 SkycalcTERCurve: "armazones_atmo_skycalc_ter_curve"


Included by default: False

File Description: atmospheric spectra pulled from the skycalc server

Class Description: <no docstring>

Changes:

-



Data

Meta-data

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 91 of 106
-------------------	--	--

```

filename : None
  name : armazones_atmo_skycalc_ter_curve
  include : False
  altitude : 3060
  longitude : -70.1918
  latitude : -24.5899
  temperature : 7
  humidity : 0.1
  pressure : 0.755
  pwv : 2.5
  airmass : 1.2
  pupil_angle : 0
  pixel_scale : 0.004
  background : \{'filter_name': 'Ks', 'value': 13.6, 'unit': 'mag'\}
  spectrum : \{'filename': 'TER_armazones_default_FULL_IMG.dat'\}
element_name : armazones
observatory : armazones
  wmin : 699.9999999999999
  wmax : 2499.999999999995
  wunit : um
  wdelta : 0.09999999999999999
  z_order : [112, 512]
ignore_wings : False
  wave_min : 0.7
  wave_max : 2.5
  wave_unit : um
  wave_bin : 0.0001
report_plot_include : True
report_table_include : False
  action : transmission
  position : 0

```

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 92 of 106
-------------------	---	--

4.2 OpticalElement: "ELT"

Element: telescope

Alias: TEL

Description: The extremely large telescope

4.2.1 Global properties

```
temperature : !ATMO.temperature
element_name : ELT
```

4.2.2 Effects

Summary of Effects included in this optical element:

element	name	class	included	z_orders
ELT	scope_surface_list	SurfaceList	True	[20, 120, 520]
ELT	scope_vibration	Vibration	True	[244, 744]
ELT	eso_combined_reflection	TERCurve	False	[10, 110, 510]

4.2.2.1 SurfaceList: "scope_surface_list"


Included by default: True

File Description: list of ELT surfaces

Class Description: <no docstring>

Changes:

- 2018-11-19 (KL) Added meta data, added Action column
- 2019-01-28 (KL) Fixed YAML format in meta data
- 2020-08-17 (KL) Updated M1 and M4 dimensions according to ESO-253082_4 sect 4.7 "all-glass" diameter
- 2020-08-17 (KL) Pegged temperature to the atmosphere



name	outer	inner	angle	temperature	action	filename
ELT_M1	36.9	10.95	0.0	!ATMO.temperature	reflection	TER_ELT_mirror_mgf2agal.dat
ELT_M2	4.2	0.545	0.0	!ATMO.temperature	reflection	TER_ELT_mirror_mgf2agal.dat
ELT_M3	3.8	0.14	0.0	!ATMO.temperature	reflection	TER_ELT_mirror_mgf2agal.dat
ELT_M4	2.54	0.536	7.75	!ATMO.temperature	reflection	TER_ELT_mirror_aluminium.da
ELT_M5	2.66	0.0	37.25	!ATMO.temperature	reflection	TER_ELT_mirror_mgf2agal.dat

Data

Meta-data

```

filename : LIST_mirrors_ELT.tbl
name : scope_surface_list
temperature : !ATMO.temperature
element_name : ELT
author : Oliver Czoske, Kieran Leschinski
source : ESO ELT DRM, ESO-253082_4
date_created : 2018-11-19
date_modified : 2020-08-17
status : Design, pre MICADO-FDR mirror list
outer_unit : m
inner_unit : m
angle_unit : degree

```

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 94 of 106
-------------------	---	--

```

temperature_unit : deg_C
    notes : ['2020-08-17 (KL) Coatings match those described in ES
z_order : [20, 120, 520]
    include : True
    ignore_wings : False
    wave_min : !SIM.spectral.wave_min
    wave_max : !SIM.spectral.wave_max
    wave_unit : !SIM.spectral.wave_unit
    wave_bin : !SIM.spectral.spectral_resolution
report_plot_include : True
report_table_include : True
    minimum_throughput : !SIM.spectral.minimum_throughput
    etendue : !TEL.etendue

```

4.2.2.2 Vibration: "scope_vibration"


Included by default: True

File Description: residual vibration of telescope

Class Description: Creates a wavelength independent kernel image

Changes:

-



Data

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 95 of 106
-------------------	---	--

Meta-data

filename	: None
name	: scope_vibration
temperature	: 7
element_name	: ELT
fwhm	: 0.001
pixel_scale	: 0.004
z_order	: [244, 744]
include	: True
flux_accuracy	: 0.001
sub_pixel_flag	: False
convolve_mode	: full
wave_key	: WAVE0
normalise_kernel	: True
report_plot_include	: True
report_table_include	: False
width_n_fwhms	: 4

4.2.2.3 TERCurve: "eso_combined_reflection"

Included by default: False


File Description: single combined reflection curve for clean ELT 5 mirror combination

Class Description: Transmission, Emissivity, Reflection Curve

Changes:

- 2019-11-06 (KL) Converted from .xlsx to .dat file, added ScopeSim meta data
- 2020-07-09 (KL) Added inner and outer dimensions to meta, for use with MICADO-Sci
- 2020-08-17 (KL) Added emissivity column according to ESO-253082_4, sect 4.12.2

Micado Consortium	ScopeSim instrument packages for MICADO	Doc:	ELT-TRE-MCD-56306-0059
		Issue:	1.0
		Date:	12. April 2021
		Page:	96 of 106



Data

Meta-data

```

filename : TER_ELT_system_20190611.dat
name : eso_combined_reflection
include : False
temperature : 7
element_name : ELT
temperture : 7
author : R. Holzloehner
source : See ESO-306070 and ESO-293390 for background.
date_created : 2018-09-18
date_modified : 2019-06-11
type : TERCurve
status : design
action : reflection
outer : 37.3
outer_unit : m
inner : 11.1
inner_unit : m
wavelength_unit : um
notes : ['Baseline coatings.', 'Fresh coatings without contami
z_order : [10, 110, 510]
ignore_wings : False

```


Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 97 of 106
-------------------	--	--

```

        wave_min : 0.7
        wave_max : 2.5
        wave_unit : um
        wave_bin  : 0.0001
    report_plot_include : True
    report_table_include : False

```

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 98 of 106
-------------------	---	--

4.3 OpticalElement: "MAORY"

Element: relay_optics

Alias: RO

Description: MAORY AO relay module

4.3.1 Global properties

```
temperature : !ATMO.temperature
psf_filename : None
element_name : MAORY
```

4.3.2 Effects

Summary of Effects included in this optical element:

element	name	class	included	z_orders
MAORY	maory_surface_list	SurfaceList	True	[20, 120, 520]
MAORY	maory_generic_psf	FieldConstantPSF	True	[262, 662]

4.3.2.1 SurfaceList: "maory_surface_list"

Included by default: True


File Description: list of surfaces in MAORY

Class Description: <no docstring>

Changes:

- 2018-11-19 (KL) Added meta data, changed Dichr. filename
- 2019-01-28 (KL) Fixed YAML format in meta data
- 2020-06-22 (KL) Updated file to match the MMS configuration from Carmelo
- 2020-08-17 (KL) Pegged temperature to atmosphere
- 2020-12-03 (KL)

Micado Consortium	ScopeSim instrument packages for MICADO	Doc:	ELT-TRE-MCD-56306-0059
		Issue:	1.0
		Date:	12. April 2021
		Page:	99 of 106



name	outer	inner	angle	temperature	action	filename
SchPlate	1.1	0.0	0.0	!ATMO.temperature	transmission	TER_entrance_window.dat
M6	1.1	0.0	0.0	!ATMO.temperature	reflection	TER_MAORY_mirror_silver.da
M7	0.7	0.0	0.0	!ATMO.temperature	reflection	TER_MAORY_mirror_silver.da
M8	0.85	0.0	0.0	!ATMO.temperature	reflection	TER_MAORY_mirror_silver.da
DM9	0.75	0.0	0.0	!ATMO.temperature	reflection	TER_MAORY_mirror_mgf2aga
DM10	0.75	0.0	0.0	!ATMO.temperature	reflection	TER_MAORY_mirror_mgf2aga
Dichroic	0.6	0.0	0.0	!ATMO.temperature	reflection	TER_MAORY_lgs_dichroic.dat
M10	0.6	0.0	0.0	!ATMO.temperature	reflection	TER_MAORY_mirror_silver.da
M11	0.8	0.0	45.0	!ATMO.temperature	reflection	TER_MAORY_mirror_silver.da
M12	0.8	0.0	0.0	!ATMO.temperature	reflection	TER_MAORY_mirror_silver.da

Data

Meta-data

```

filename : LIST_mirrors_maory_mms.tbl
name      : maory_surface_list
temperature : !ATMO.temperature
psf_filename : None
element_name : MAORY
author    : Kieran Leschinski

```

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 100 of 106
-------------------	---	---

```

        source : Carmelo Archidiacono private email
    date_created : 2018-11-19
    date_modified : 2020-06-22
        status : Design, new MAORY MMS design
    outer_unit : m
    inner_unit : m
    angle_unit : degree
    temperature_unit : deg_C
        z_order : [20, 120, 520]
        include : True
    ignore_wings : False
        wave_min : !SIM.spectral.wave_min
        wave_max : !SIM.spectral.wave_max
        wave_unit : !SIM.spectral.wave_unit
        wave_bin : !SIM.spectral.spectral_resolution
    report_plot_include : True
    report_table_include : True
        minimum_throughput : !SIM.spectral.minimum_throughput
        etendue : !TEL.etendue

```

4.3.2.2 FieldConstantPSF: "maory_generic_psf"

Included by default: True


File Description: MAORY field varying MCAO PSF

Class Description: <no docstring>

Changes:

-

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 101 of 106
-------------------	---	---



Data

Meta-data

```

filename : PSF_MCAO_ConstPSF_40_18_6.fits
name : maory_generic_psf
temperature : 7
psf_filename : None
element_name : MAORY
warning : Default PSF is not Field Varying. See Documentation
SIMPLE : True
BITPIX : 8
NAXIS : 0
EXTEND : True
AUTHOR : Kieran Leschinski
DATE_CRE : 2019-07-30
DATE_MOD : 2019-07-30
SOURCE : AnisoCADO
STATUS : Best guess for a MAORY ConstantPSF with AnisoCADO
ETypes : CONSTPSF
ECAT : -1
EDATA : 1
XOFFSET : 0
YOFFSET : 0
z_order : [262, 662]
```

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 102 of 106
-------------------	--	---

```

        include : True
    flux_accuracy : 0.001
    sub_pixel_flag : False
    convolve_mode : full
        wave_key : WAVE0
    normalise_kernel : True
    report_plot_include : True
    report_table_include : False

```

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 103 of 106
-------------------	---	---

4.4 OpticalElement: "default_ro"

Element: relay_optics

Alias: RO

Description: Simple stand-alone relay optics module

4.4.1 Global properties

```

temperature : !ATMO.temperature
psf_filename : None
element_name : default_ro

```

4.4.2 Effects

Summary of Effects included in this optical element:

element	name	class	included	z_orders
default_ro	relay_psf	FieldConstantPSF	True	[262, 662]
default_ro	relay_surface_list	SurfaceList	True	[20, 120, 520]

4.4.2.1 FieldConstantPSF: "relay_psf"

Included by default: True


File Description: SCAO PSF

Class Description: <no docstring>

Changes:

-

Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 104 of 106
-------------------	---	---



Data

Meta-data

```

filename : PSF_SCAO_ConstPSF_0_5off.fits
name : relay_psf
temperature : 7
psf_filename : None
element_name : default_ro
warning : Default PSF is NOT field varying. See documentation.
SIMPLE : True
BITPIX : 8
NAXIS : 0
EXTEND : True
AUTHOR : Kieran Leschinski
DATE_CRE : 2019-07-30
DATE_MOD : 2019-07-30
SOURCE : AnisoCADO
STATUS : Best guess for a standard observations
ETypes : CONSTPSF
ECAT : -1
EDATA : 1
XOFFSET : 0
YOFFSET : 5
z_order : [262, 662]
```


Micado Consortium	ScopeSim instrument packages for MICADO	Doc: ELT-TRE-MCD-56306-0059 Issue: 1.0 Date: 12. April 2021 Page: 106 of 106
-------------------	---	---

name	outer	inner	angle	temperature	action	filename
MIC_RO_M1	0.505	0.0	45.0	!ATMO.temperature	reflection	TER_MICADO_mirror_mgf2aga
MIC_RO_M2	0.51	0.0	10.0	!ATMO.temperature	reflection	TER_MICADO_mirror_mgf2aga
MIC_RO_M3	0.184	0.0	10.0	!ATMO.temperature	reflection	TER_MICADO_mirror_mgf2aga
MIC_RO_M4	0.53	0.0	10.0	!ATMO.temperature	reflection	TER_MICADO_mirror_mgf2aga
MIC_RO_M5	0.406	0.0	20.0	!ATMO.temperature	reflection	TER_MICADO_mirror_mgf2aga
MIC_RO_M6	0.406	0.0	35.0	!ATMO.temperature	reflection	TER_MICADO_mirror_mgf2aga

Data

Meta-data

```

filename : LIST_RO_SCAO_mirrors.dat
name : relay_surface_list
temperature : !ATMO.temperature
psf_filename : None
element_name : default_ro
author : Oliver Czoske, Kieran Leschinski
source : P12_RelayOptics_Status_2020-06-23-MICADO-CM16-RO-v2.pdf
date_created : 2018-11-19
date_modified : 2020-08-17
status : Design, pre FDR list of stand-alone SCAO relay optics
type : mirror:list
outer_unit : m
inner_unit : m
angle_unit : degree
temperature_unit : deg_C
z_order : [20, 120, 520]
include : True
ignore_wings : False
wave_min : !SIM.spectral.wave_min
wave_max : !SIM.spectral.wave_max
wave_unit : !SIM.spectral.wave_unit
wave_bin : !SIM.spectral.spectral_resolution
report_plot_include : True
report_table_include : True
minimum_throughput : !SIM.spectral.minimum_throughput
etendue : !TEL.etendue

```