

# ScopeSim instrument packages for MICADO

Doc. No.: ELT-TRE-MCD-56306-0059

Kieran Leschinski, Hugo Buddelmeijer, Oliver Czoske, Miguel Verdugo,  
Gijs Verdoes-Kleijn, Werner Zeilinger

October 14, 2020

# Contents

<b>1</b>	<b>Introduction</b>	<b>3</b>
1.1	Overview of the Instrument Packages	4
1.1.1	Primary MICADO packages	4
1.1.2	Support packages	4
1.1.3	Adding content to the packages	4
1.2	Contents of packages	5
<b>2</b>	<b>MICADO Pipeline package</b>	<b>6</b>
2.1	Summary of Effects in Optical Elements:	7
2.2	OpticalElement: "MICADO"	8
2.2.1	Global properties	8
2.2.2	Effects	8
2.3	OpticalElement: "MICADO_IMG_LR"	12
2.3.1	Global properties	12
2.3.2	Effects	12
2.4	OpticalElement: "MICADO_IMG_HR"	15
2.4.1	Global properties	15
2.4.2	Effects	15
2.5	OpticalElement: "MICADO_SPEC"	18
2.5.1	Global properties	18
2.5.2	Effects	18
2.6	OpticalElement: "micado_detector_array"	22
2.6.1	Global properties	22
2.6.2	Effects	22
2.7	OpticalElement: "MICADO_simulation_paramters"	31
2.7.1	Global properties	31
2.7.2	Effects	31
<b>3</b>	<b>MICADO Science package</b>	<b>32</b>
3.1	OpticalElement: "MICADO"	33
3.1.1	Global properties	33
3.1.2	Effects	33
3.2	OpticalElement: "MICADO_SCAO"	36
3.2.1	Global properties	36
3.2.2	Effects	36
3.3	OpticalElement: "MICADO_MCAO"	39
3.3.1	Global properties	39
3.3.2	Effects	39
3.4	OpticalElement: "4mas"	42

3.4.1	Global properties	42
3.4.2	Effects	42
3.5	OpticalElement: "1.5mas"	43
3.5.1	Global properties	43
3.5.2	Effects	43
<b>4</b>	<b>Supoort packages</b>	<b>44</b>
4.1	OpticalElement: "armazones"	45
4.1.1	Global properties	45
4.1.2	Effects	45
4.2	OpticalElement: "ELT"	49
4.2.1	Global properties	49
4.2.2	Effects	49
4.3	OpticalElement: "MAORY"	52
4.3.1	Global properties	52
4.3.2	Effects	52
4.4	OpticalElement: "default_ro"	55
4.4.1	Global properties	55
4.4.2	Effects	55

# **Chapter 1**

## **Introduction**

## 1.1 Overview of the Instrument Packages

The MICADO instrument simulator has moved from using the stand alone SimCADO package to using the generic astronomical instrument simulator ScopeSim. As the ScopeSim code is instrument agnostic, all data related to creating instrument models are contained inside instrument packages, which are hosted on the [instrument reference database \(IRDB\)](#).

### 1.1.1 Primary MICADO packages

This document is primarily concerned with describing the contents of the two major MICADO instrument descriptions: MICADO and MICADO\_Sci. These two packages serve two different audiences:

1. The MICADO package contains all information available pertaining to the optical effects expected for the MICADO optical system. The primary user of this package will be the data flow system. The primary use case for this package is the creation of raw data frames for testing the algorithms of the reduction pipelines for the different modes of MICADO. This package is large and therefore computationally expensive and slow.
2. The MICADO\_Sci package contains a subset of the effects in the MICADO package. The primary users of this package will be the science team and outside astronomers interested in simulating observations with the future MICADO instrument. The goal of this package is enable observations to be simulated quickly, so that the user can quickly iterate on observation strategies and/or target choices. As such this package contains only the effects which cause the major optical aberrations. It is by nature not complete, but aims to provide a level of detail sufficient for the majority of observation feasibility studies for MICADO

### 1.1.2 Support packages

The MICADO packages, as the names suggest, only describe the contents of the MICADO instrument. Observations with MICADO will however rely on the ELT infrastructure, which can be decomposed into several parts: Location, Telescope, Relay optics. Each of these additional parts can be considered as closed optical elements in the full observational optical system. Indeed the relay optics element is a replaceable element in the optical path (with MAORY vs stand-alone mode) Hence each of these optical elements have been given their own instrument package, and are referred to as support packages.

The support packages needed to simulate MICADO observations are also described in this document. Specifically these are:

- Armazones
- ELT
- MAORY
- Stand-alone relay optics

For each observation the Armazones and ELT packages are required. However only one of MAORY or the stand-alone relay optics packages are required.

### 1.1.3 Adding content to the packages

The contents of the packages are currently in the public domain. The raw data is [hosted on Github](#).

Periodically this data is compiled into an instrument package and uploaded to the ScopeSim server. It is these packages which are downloaded by ScopeSim when setting up an observation simulation.

New data or Effect objects can be added by submitting a pull request to the [Github repository](#).

## 1.2 Contents of packages

Each package contains three types of files:

1. configuration,
2. effect descriptions, and
3. raw data

The configuration files are responsible for controlling which effects and which parameters and values are used when generating the optical model for an observation simulation. The effect files describe which classes and which values should be used when applying an effect to the photon flux of the target object, e.g. which PSF kernel should be applied at which wavelength. The raw data files provide the raw data needed by the Effect objects, e.g. the bitmaps of the PSF kernels.

In the following sections each optical element is described. Each optical element contains a description of all the optical Effects associated with it, as well as a list of the configuration keywords and values required by the effect. If an Effect required data from an external file (e.g. PSF kernels, linearity curves, etc), these data are presented as part of each Effect object - either in the `Table` or `Data` sections.

**Note**

The raw data will not always be displayed directly.

A representation of the data will be presented where available. For further details the reader is directed to the view the data directly on the [IRDB](#)

## **Chapter 2**

# **MICADO Pipeline package**

## 2.1 Summary of Effects in Optical Elements:

element	name	class	included	z_orders
armazones	armazones_atmo_default_ter_curve	AtmosphericTERCurve	True	[111, 511]
armazones	armazones_atmo_dispersion	AtmosphericDispersion	True	[231]
armazones	armazones_atmo_skycalc_ter_curve	SkycalcTERCurve	False	[112, 512]
ELT	scope_surface_list	SurfaceList	True	[20, 120, 520]
ELT	scope_vibration	Vibration	True	[244, 744]
ELT	eso_combined_reflection	TERCurve	False	[10, 110, 510]
MICADO	micado_static_surfaces	SurfaceList	True	[20, 120, 520]
MICADO	micado_filter	FilterCurve	True	[114, 214, 514]
MICADO	micado_ncpas_psf	NonCommonPathAberration	True	[241, 641]
micado_detector_array	full_detector_array	DetectorList	False	[90, 290, 390, 490]
micado_detector_array	detector_window	DetectorList	True	[90, 290, 390, 490]
micado_detector_array	qe_curve	QuantumEfficiencyCurve	True	[113, 513]
micado_detector_array	exposure_action	SummedExposure	True	[860]
micado_detector_array	dark_current	DarkCurrent	True	[830]
micado_detector_array	detector_linearity	LinearityCurve	True	[840]
micado_detector_array	shot_noise	ShotNoise	True	[820]
micado_detector_array	readout_noise	PoorMansHxRGReadoutNoise	True	[811]
default_ro	relay_psf	FieldConstantPSF	True	[262, 662]
default_ro	relay_surface_list	SurfaceList	True	[20, 120, 520]
MAORY	maory_surface_list	SurfaceList	True	[20, 120, 520]
MAORY	maory_generic_psf	FieldConstantPSF	True	[262, 662]
MICADO_IMG_LR	micado_wide_field_mirror_list	SurfaceList	True	[20, 120, 520]
MICADO_IMG_LR	micado_adc_3D_shift	AtmosphericDispersionCorrection	True	[632, 232]
MICADO_IMG_HR	zoom_mirror_list	SurfaceList	True	[20, 120, 520]
MICADO_IMG_HR	micado_adc_3D_shift	AtmosphericDispersionCorrection	True	[632, 232]
MICADO_SPEC	spec_mode_optics	SurfaceList	True	[20, 120, 520]
MICADO_SPEC	spectroscopic_slit_aperture	ApertureMask	True	[80, 280, 380]
MICADO_SPEC	micado_spectral_traces	SpectralTraceList	True	[70, 270]
MICADO_SPEC	spec_mode_optics	SurfaceList	True	[20, 120, 520]
MICADO_SPEC	spectroscopic_slit_aperture	ApertureMask	True	[80, 280, 380]
MICADO_SPEC	micado_spectral_traces	SpectralTraceList	True	[70, 270]
MICADO_SPEC	spec_mode_optics	SurfaceList	True	[20, 120, 520]
MICADO_SPEC	spectroscopic_slit_aperture	ApertureMask	True	[80, 280, 380]
MICADO_SPEC	micado_spectral_traces	SpectralTraceList	True	[70, 270]



## 2.2 OpticalElement: "MICADO"

**Element:** instrument

**Alias:** INST

**Description:** Effects from the MICADO common optics

### 2.2.1 Global properties

```
temperature : -190
element_name : MICADO
```

### 2.2.2 Effects

Summary of Effects included in this optical element:

element	name	class	included	z_orders
MICADO	micado_static_surfaces	SurfaceList	True	[20, 120, 520]
MICADO	micado_filter	FilterCurve	True	[114, 214, 514]
MICADO	micado_ncpas_psf	NonCommonPathAberration	True	[241, 641]

#### 2.2.2.1 SurfaceList: "micado\_static\_surfaces"

**Included by default:** True

**File Description:** surfaces list for wide field optics

**Class Description:** <no docstring>

**Changes:**

- {datetime.date(2019, 1, 28): '(KL) Changed column names and added units to header'}
- {datetime.date(2019, 7, 10): '(KL) Shortened the list to only the swappable mirrors'}
- {datetime.date(2020, 8, 25): '(KL) Updated angle\_unit to degree from degrees (why has astropy not complained until now?)'}

**Data**

**Meta-data**

```
filename : LIST_MICADO_mirrors_static.dat
name : micado_static_surfaces
temperature : -190
element_name : MICADO
author : Kieran Leschinski
source : Ric's SPIE 2018 PPT presentation
```

```

    date_created : 2018-11-19
    date_modified : 2019-07-10
        status : Design - pre PDR list of all static MICADO surfaces
        type : mirror:list
    outer_unit : m
    inner_unit : m
    angle_unit : degree
    temperature_unit : deg_C
        z_order : [20, 120, 520]
        include : True
    ignore_wings : False
        wave_min : !SIM.spectral.wave_min
        wave_max : !SIM.spectral.wave_max
        wave_unit : !SIM.spectral.wave_unit
        wave_bin : !SIM.spectral.spectral_resolution
    minimum_throughput : !SIM.spectral.minimum_throughput
        etendue : !TEL.etendue

```

#### 2.2.2.2 FilterCurve: "micado\_filter"

**Included by default:** True

**File Description:** transmission curve for filter

**Class Description:** Other Parameters

**Changes:**

- 

**Data**

**Meta-data**

```

    filename : filters/TC_filter_Spec_HK.dat
        name : micado_filter
    temperature : -190
    element_name : MICADO
    filter_name : !OBS.filter_name
    filename_format : filters/TC_filter_{\}.dat
    minimum_throughput : 0.000101
        outer : 0.2
        outer_unit : m
        author : Ric Davies
        source : Ric Davies
    date_created : 2017-11-20
    date_modified : 2017-11-20
        status : Design - pre PDR list of filters
        z_order : [114, 214, 514]

```

```

        include : True
    ignore_wings : False
        wave_min : !SIM.spectral.wave_min
        wave_max : !SIM.spectral.wave_max
        wave_unit : !SIM.spectral.wave_unit
        wave_bin : !SIM.spectral.spectral_resolution
        action : transmission
        position : -1
    wing_flux_level : None

```

### 2.2.2.3 NonCommonPathAberration: "micado\_ncpas\_psf"

**Included by default:** True

**File Description:** Effective NCPA induced PSF kernel

**Class Description:** Needed: pixel\_scale

**Changes:**

- 2018-11-19 (KL) updated meta data to new format

**Data**

**Meta-data**

```

        filename : INST_MICADO_wavefront_error_budget.dat
        name : micado_ncpas_psf
    temperature : -190
    element_name : MICADO
    pixel_scale : 0.004
        author : Kieran Leschinski
        sources : Ric Davies email
    date_created : 2016-11-21
    date_modified : 2018-11-19
        type : instrument:wavefront_errors_list
        status : Idea - based on the WFE budget and emails with Ric
    wfe_rms_unit : nm
        z_order : [241, 641]
        include : True
    flux_accuracy : 0.001
    sub_pixel_flag : False
    convolve_mode : full
        wave_key : WAVE0
    normalise_kernel : True
    kernel_width : None
    strehl_drift : 0.02
        wave_min : !SIM.spectral.wave_min
        wave_max : !SIM.spectral.wave_max

```



## 2.3 OpticalElement: "MICADO\_IMG\_LR"

**Element:** instrument

**Alias:** INST

**Description:** additional effects for the wide-field imaging mode

### 2.3.1 Global properties

```
pixel_scale : 0.004
plate_scale : 0.266666666666
element_name : MICADO_IMG_LR
```

### 2.3.2 Effects

Summary of Effects included in this optical element:

element	name	class	included	z_orders
MICADO_IMG_LR	micado_wide_field_mirror_list	SurfaceList	True	[20, 120, 520]
MICADO_IMG_LR	micado_adc_3D_shift	AtmosphericDispersionCorrection	True	[632, 232]

#### 2.3.2.1 SurfaceList: "micado\_wide\_field\_mirror\_list"

**Included by default:** True

**File Description:** list of extra mirrors needed for the wide field mode

**Class Description:** <no docstring>

**Changes:**

- {datetime.date(2019, 1, 28): '(KL) Changed column names and added units to header'}
- {datetime.date(2019, 7, 10): '(KL) Shortened the list to only the swappable mirrors'}

**Data**

**Meta-data**

```
filename : LIST_MICADO_mirrors_wide.dat
name : micado_wide_field_mirror_list
pixel_scale : 0.004
plate_scale : 0.266666666666
element_name : MICADO_IMG_LR
author : Kieran Leschinski
source : Ric's SPIE 2018 PPT presentation
date_created : 2018-11-19
```

```

    date_modified : 2019-07-10
        status : Design - pre PDR list of MICADO mirrors for wide-field mo
        type : mirror:list
    outer_unit : m
    inner_unit : m
    angle_unit : degree
temperature_unit : deg_C
    z_order : [20, 120, 520]
    include : True
    ignore_wings : False
    wave_min : !SIM.spectral.wave_min
    wave_max : !SIM.spectral.wave_max
    wave_unit : !SIM.spectral.wave_unit
    wave_bin : !SIM.spectral.spectral_resolution
minimum_throughput : !SIM.spectral.minimum_throughput
    etendue : !TEL.etendue

```

### 2.3.2.2 AtmosphericDispersionCorrection: "micado\_adc\_3D\_shift"

**Included by default:** True

**File Description:** atmospheric dispersion corrector

**Class Description:** <no docstring>

**Changes:**

- 

**Data**

**Meta-data**

```

    filename : None
        name : micado_adc_3D_shift
    pixel_scale : 0.004
    plate_scale : 0.266666666666
    element_name : MICADO_IMG_LR
        altitude : !ATMO.altitude
        longitude : !ATMO.longitude
        latitude : !ATMO.latitude
        airmass : !OBS.airmass
    temperature : !ATMO.temperature
        humidity : !ATMO.humidity
        pressure : !ATMO.pressure
    pupil_angle : !OBS.pupil_angle
    efficiency : 1
        wave_mid : !SIM.spectral.wave_mid
    quick_adc : True

```

```
z_order : [632, 232]  
include : True
```

## 2.4 OpticalElement: "MICADO\_IMG\_HR"

**Element:** instrument

**Alias:** INST

**Description:** additional effects for the zoom imaging mode

### 2.4.1 Global properties

```
pixel_scale : 0.0015
plate_scale : 0.1
element_name : MICADO_IMG_HR
```

### 2.4.2 Effects

Summary of Effects included in this optical element:

element	name	class	included	z_orders
MICADO_IMG_HR	zoom_mirror_list	SurfaceList	True	[20, 120, 520]
MICADO_IMG_HR	micado_adc_3D_shift	AtmosphericDispersionCorrection	True	[632, 232]

#### 2.4.2.1 SurfaceList: "zoom\_mirror\_list"

**Included by default:** True

**File Description:** list of extra mirror needed for the zoom imaging mode

**Class Description:** <no docstring>

**Changes:**

- {datetime.date(2019, 1, 28): '(KL) Changed column names and added units to header'}
- {datetime.date(2019, 7, 10): '(KL) Shortened the list to only the swappable mirrors'}

**Data**

**Meta-data**

```
filename : LIST_MICADO_mirrors_zoom.dat
name : zoom_mirror_list
pixel_scale : 0.0015
plate_scale : 0.1
element_name : MICADO_IMG_HR
author : Kieran Leschinski
source : Ric's SPIE 2018 PPT presentation
date_created : 2018-11-19
```



```

    date_modified : 2019-07-10
        status : Design - pre PDR list of swappable mirrors for zoom mode
            type : mirror:list
            ETYPE : SURFLIST
            EDIM : 1
        outer_unit : m
        inner_unit : m
        angle_unit : degree
    temperature_unit : deg_C
        z_order : [20, 120, 520]
        include : True
    ignore_wings : False
        wave_min : !SIM.spectral.wave_min
        wave_max : !SIM.spectral.wave_max
        wave_unit : !SIM.spectral.wave_unit
        wave_bin : !SIM.spectral.spectral_resolution
    minimum_throughput : !SIM.spectral.minimum_throughput
        etendue : !TEL.etendue

```

#### 2.4.2.2 AtmosphericDispersionCorrection: "micado\_adc\_3D\_shift"

**Included by default:** True

**File Description:** atmospheric dispersion corrector

**Class Description:** <no docstring>

**Changes:**

- 

**Data**

**Meta-data**

```

    filename : None
        name : micado_adc_3D_shift
    pixel_scale : 0.0015
    plate_scale : 0.1
    element_name : MICADO_IMG_HR
        altitude : !ATMO.altitude
        longitude : !ATMO.longitude
        latitude : !ATMO.latitude
        airmass : !OBS.airmass
    temperature : !ATMO.temperature
        humidity : !ATMO.humidity
        pressure : !ATMO.pressure
    pupil_angle : !OBS.pupil_angle
        wave_mid : !SIM.spectral.wave_mid

```

```
efficiency : 1
quick_adc : True
  z_order : [632, 232]
  include : True
```

## 2.5 OpticalElement: "MICADO\_SPEC"

**Element:** instrument

**Alias:** INST

**Description:** additional effects for the spectroscopy mode

### 2.5.1 Global properties

```
pixel_scale : 0.004
plate_scale : 0.2666666667
element_name : MICADO_SPEC
```

### 2.5.2 Effects

Summary of Effects included in this optical element:

element	name	class	included	z_orders
MICADO_SPEC	spec_mode_optics	SurfaceList	True	[20, 120, 520]
MICADO_SPEC	spectroscopic_slit_aperture	ApertureMask	True	[80, 280, 380]
MICADO_SPEC	micado_spectral_traces	SpectralTraceList	True	[70, 270]

#### 2.5.2.1 SurfaceList: "spec\_mode\_optics"

**Included by default:** True

**File Description:** list of extra mirrors needed for the spectroscopy mode

**Class Description:** <no docstring>

**Changes:**

- {datetime.date(2019, 1, 28): '(KL) Changed column names and added units to header'}
- {datetime.date(2019, 7, 10): '(KL) Shortened the list to only the swappable gratings'}

**Data**

**Meta-data**

```
filename : LIST_MICADO_mirrors_spec.dat
name : spec_mode_optics
pixel_scale : 0.004
plate_scale : 0.2666666667
element_name : MICADO_SPEC
author : Kieran Leschinski
source : Ric's SPIE 2018 PPT presentation
```

```

    date_created : 2018-11-19
    date_modified : 2019-07-10
        status : Design - pre PDR list of swappable optics for spectroscopy
        type : mirror:list
        ETYPE : SURFLIST
        EDIM : 1
    outer_unit : m
    inner_unit : m
    angle_unit : degree
    temperature_unit : deg_C
        z_order : [20, 120, 520]
        include : True
    ignore_wings : False
        wave_min : !SIM.spectral.wave_min
        wave_max : !SIM.spectral.wave_max
        wave_unit : !SIM.spectral.wave_unit
        wave_bin : !SIM.spectral.spectral_resolution
    minimum_throughput : !SIM.spectral.minimum_throughput
        etendue : !TEL.etendue

```

### 2.5.2.2 ApertureMask: "spectroscopic\_slit\_aperture"

**Included by default:** True

**File Description:** Slit mask for the short, narrow slit (3 arcsec x 20 mas)

**Class Description:** Only provides the on-sky window coords of the Aperture

**Changes:**

- {datetime.date(2019, 7, 10): '(KL) Created the file'}
- {datetime.date(2020, 3, 24): '(KL) Changed geometry to 3000x20mas'}

**Data**

**Meta-data**

```

    filename : !OBS.slit_file
        name : spectroscopic_slit_aperture
    pixel_scale : 0.004
    plate_scale : 0.2666666667
    element_name : MICADO_SPEC
        author : Kieran Leschinski
        source : My imagination
    date_created : 2019-07-10
    date_modified : 2019-07-10
        status : Guess - in the train on the way home from CM13
        type : aperture:slit_geometry
    x_unit : arcsec

```

```

        y_unit : arcsec
        z_order : [80, 280, 380]
        include : True
        no_mask : True
        angle : 0
        shape : rect
        conserve_image : True
        id : 0

```

<SpectralTrace> "list of spectral order trace geometry on the focal plane" : [1.93, 2.46]um : Ext 2 : Aperture 0 : ImagePlane 0 <SpectralTrace> "list of spectral order trace geometry on the focal plane" : [1.45, 1.85]um : Ext 3 : Aperture 0 : ImagePlane 0 <SpectralTrace> "list of spectral order trace geometry on the focal plane" : [1.16, 1.48]um : Ext 4 : Aperture 0 : ImagePlane 0 <SpectralTrace> "list of spectral order trace geometry on the focal plane" : [1.16, 1.39]um : Ext 5 : Aperture 0 : ImagePlane 0 <SpectralTrace> "list of spectral order trace geometry on the focal plane" : [0.97, 1.23]um : Ext 6 : Aperture 0 : ImagePlane 0 <SpectralTrace> "list of spectral order trace geometry on the focal plane" : [0.97, 1.23]um : Ext 7 : Aperture 0 : ImagePlane 0 <SpectralTrace> "list of spectral order trace geometry on the focal plane" : [0.83, 1.05]um : Ext 8 : Aperture 0 : ImagePlane 0 <SpectralTrace> "list of spectral order trace geometry on the focal plane" : [0.83, 1.05]um : Ext 9 : Aperture 0 : ImagePlane 0 <SpectralTrace> "list of spectral order trace geometry on the focal plane" : [0.83, 0.92]um : Ext 10 : Aperture 0 : ImagePlane 0 <SpectralTrace> "list of spectral order trace geometry on the focal plane" : [0.73, 0.92]um : Ext 11 : Aperture 0 : ImagePlane 0 <SpectralTrace> "list of spectral order trace geometry on the focal plane" : [0.73, 0.92]um : Ext 12 : Aperture 0 : ImagePlane 0 <SpectralTrace> "list of spectral order trace geometry on the focal plane" : [0.65, 0.82]um : Ext 13 : Aperture 0 : ImagePlane 0 <SpectralTrace> "list of spectral order trace geometry on the focal plane" : [0.65, 0.82]um : Ext 14 : Aperture 0 : ImagePlane 0 <SpectralTrace> "list of spectral order trace geometry on the focal plane" : [0.6, 0.74]um : Ext 15 : Aperture 0 : ImagePlane 0 <SpectralTrace> "list of spectral order trace geometry on the focal plane" : [0.6, 0.73]um : Ext 16 : Aperture 0 : ImagePlane 0 <SpectralTrace> "list of spectral order trace geometry on the focal plane" : [0.6, 0.67]um : Ext 17 : Aperture 0 : ImagePlane 0 <SpectralTrace> "list of spectral order trace geometry on the focal plane" : [0.6, 0.67]um : Ext 18 : Aperture 0 : ImagePlane 0

**Included by default:** True

**File Description:** list of spectral order trace geometry on the focal plane

**Class Description:** List of spectral trace geometries for the detector plane

**Changes:**

- 

**Data**

**Meta-data**

```

        filename : !OBS.trace_file
        name : micado_spectral_traces
        pixel_scale : 0.004
        plate_scale : 0.2666666667
        element_name : MICADO_SPEC
        wave_colname : lam

```

```

s_colname : xi
col_number_start : 1
invalid_value : 0
    SIMPLE : True
    BITPIX : 8
    NAXIS : 0
    EXTEND : True
FILETYPE : Spectral Layout Definition
    AUTHOR : Oliver Czoske
    DATE : 2018-09-16
    SOURCE : Frank Grupp
    ORIGDATE : 2018-06-29
    STATUS : Design PDR
    ECAT : 1
    EDATA : 2
    DESCRPT : Maps spectral traces from long slit aperture to detector im
    DATE_CRE : 2018-06-29
    DATE_MOD : 2019-09-16
    HISTORY : 2019-09-16 : (KL) Added aperture-imagePlane table to EXT 1
    z_order : [70, 270]
    include : True
    wave_min : !SIM.spectral.wave_min
    wave_max : !SIM.spectral.wave_max
x_colname : x
y_colname : y
    dwave : 0.002

```

## 2.6 OpticalElement: "micado\_detector\_array"

**Element:** detector

**Alias:** DET

**Description:** A set of 9 H4RG detectors

### 2.6.1 Global properties

```
image_plane_id : 0
  temperature : -230
    dit : !OBS.dit
    ndit : !OBS.ndit
  element_name : micado_detector_array
```

### 2.6.2 Effects

Summary of Effects included in this optical element:

element	name	class	included	z_orders
micado_detector_array	full_detector_array	DetectorList	False	[90, 290, 390, 490]
micado_detector_array	detector_window	DetectorList	True	[90, 290, 390, 490]
micado_detector_array	qe_curve	QuantumEfficiencyCurve	True	[113, 513]
micado_detector_array	exposure_action	SummedExposure	True	[860]
micado_detector_array	dark_current	DarkCurrent	True	[830]
micado_detector_array	detector_linearity	LinearityCurve	True	[840]
micado_detector_array	shot_noise	ShotNoise	True	[820]
micado_detector_array	readout_noise	PoorMansHxRGReadoutNoise	True	[811]

#### 2.6.2.1 DetectorList: "full\_detector\_array"


**Included by default:** False

**File Description:** MICADO detector array list

**Class Description:** A description of detector positions and properties

**Changes:**

- {datetime.date(2017, 8, 12): '(OC) id changed to conform with spectroscopy report'}
- {datetime.date(2018, 7, 26): '(OC) large gap (chips 5 and 6) reduced to 8 mm'}
- {datetime.date(2018, 11, 19): '(KL) updated meta data to new format'}
- {datetime.date(2019, 1, 28): '(KL) moved units into header'}



id	x_cen	y_cen	x_size	y_size	x_len	y_len	pixel_size	angle	gain
1	-63.84	63.84	61.44	61.44	4096	4096	0.015	0.0	1.0
2	0.0	63.84	61.44	61.44	4096	4096	0.015	0.0	1.0
3	63.84	63.84	61.44	61.44	4096	4096	0.015	0.0	1.0
4	63.84	0.0	61.44	61.44	4096	4096	0.015	0.0	1.0
5	0.0	0.0	61.44	61.44	4096	4096	0.015	0.0	1.0
6	-69.44	0.0	61.44	61.44	4096	4096	0.015	0.0	1.0
7	-63.84	-63.84	61.44	61.44	4096	4096	0.015	0.0	1.0
8	0.0	-63.84	61.44	61.44	4096	4096	0.015	0.0	1.0
9	63.84	-63.84	61.44	61.44	4096	4096	0.015	0.0	1.0

## Data

## Meta-data

```

filename : FPA_array_layout.dat
name : full_detector_array
include : False
image_plane_id : 0

```



```

        temperature : -230
            dit : !OBS.dit
            ndit : !OBS.ndit
        element_name : micado_detector_array
    active_detectors : all
        author : Oliver Czoske
        sources : E-MCD-FPA-572089EB.uda, ELT-TRE-MCD-56300-0011
        date_created : 2017-06-28
        date_modified : 2018-07-26
            type : detector:chip_list
        x_cen_unit : mm
        y_cen_unit : mm
        xhw_unit : mm
        yhw_unit : mm
        x_len_unit : pix
        y_len_unit : pix
        pixsize_unit : mm
        angle_unit : deg
        gain_unit : electron/adu
        z_order : [90, 290, 390, 490]
        pixel_scale : !INST.pixel_scale
    report_plot_include : True
    report_table_include : True
        x_size_unit : mm
        y_size_unit : mm

```

#### 2.6.2.2 DetectorList: "detector\_window"


**Included by default:** True

**File Description:**

**Class Description:** A description of detector positions and properties

**Changes:**

-



id	pixel_size	angle	gain	x_cen	y_cen	x_size	y_size
1	0.015	0.0	1.0	0.0	0.0	15.36	15.36

## Data

## Meta-data

```

        filename : None
        name      : detector_window
        include   : True
image_plane_id : 0
    temperature : -230
        dit      : !OBS.dit
        ndit     : !OBS.ndit
element_name   : micado_detector_array
    x_cen_unit  : mm
    y_cen_unit  : mm
    xhw_unit    : mm
    yhw_unit    : mm
pixsize_unit   : mm
    angle_unit  : deg

```

```

        gain_unit : electron/adu
        z_order : [90, 290, 390, 490]
        array_dict : \{'id': [1], 'pixsize': [0.015], 'angle': [0.0], 'gain'
        pixel_scale : !INST.pixel_scale
        active_detectors : all
        report_plot_include : True
        report_table_include : True
        x_size_unit : mm
        y_size_unit : mm

```

### 2.6.2.3 QuantumEfficiencyCurve: "qe\_curve"

**Included by default:** True

**File Description:** Quantum efficiency curves for each detector

**Class Description:** <no docstring>

**Changes:**

- {datetime.date(2018, 11, 19): '(KL) updated meta data to new format'}
- {datetime.date(2019, 8, 9): '(KL) Added action keyword to meta data'}

**Data**

**Meta-data**

```

        filename : QE_detector_H2RG.dat
        name : qe_curve
image_plane_id : 0
        temperature : -230
        dit : !OBS.dit
        ndit : !OBS.ndit
        element_name : micado_detector_array
        author : Kieran Leschinski
        sources : Finger+ 2008 SPIE
        date_created : 2016-01-01
        date_modified : 2019-08-09
        type : detector:quantum_efficiency
        status : Design - guestimated by reading off the graph in Finger+ 200
wavelength_unit : um
        action : transmission
        z_order : [113, 513]
        include : True
        ignore_wings : False
        wave_min : !SIM.spectral.wave_min
        wave_max : !SIM.spectral.wave_max
        wave_unit : !SIM.spectral.wave_unit
        wave_bin : !SIM.spectral.spectral_resolution

```

```
position : -1
```

#### 2.6.2.4 SummedExposure: "exposure\_action"

**Included by default:** True

**File Description:** Summing up sky signal for all DITs and NDITs

**Class Description:** <no docstring>

**Changes:**

- 

**Data**

**Meta-data**

```
filename : None
name : exposure_action
image_plane_id : 0
temperature : -230
dit : !OBS.dit
ndit : !OBS.ndit
element_name : micado_detector_array
z_order : [860]
include : True
```

#### 2.6.2.5 DarkCurrent: "dark\_current"

**Included by default:** True

**File Description:** MICADO dark current

**Class Description:** required: dit, ndit, value

**Changes:**

- 

**Data**

**Meta-data**

```
filename : None
name : dark_current
image_plane_id : 0
temperature : -230
dit : !OBS.dit
```

```

        ndit : !OBS.ndit
    element_name : micado_detector_array
        value : 0.1
        z_order : [830]
    include : True

```

#### 2.6.2.6 LinearityCurve: "detector\_linearity"

**Included by default:** True

**File Description:** Linearity characteristics of H4RG chips

**Class Description:** <no docstring>

**Changes:**

- 2018-11-19 (KL) updated meta data to new format
- 2019-08-14 (KL) replaced long 10000000000 with 1e99

**Data**

**Meta-data**

```

        filename : FPA_linearity.dat
        name : detector_linearity
image_plane_id : 0
    temperature : -230
        dit : !OBS.dit
        ndit : !OBS.ndit
    element_name : micado_detector_array
        author : Kieran Leschinski
        sources : Ingraham+ 2014 - Gemini Calibrations II for H2RG
    date_created : 2016-01-01
    date_modified : 2018-11-19
        type : detector:linearity
        status : Design - approximated from the H2RG
    incident_unit : ph
    measured_unit : ph
        z_order : [840]
    include : True

```

#### 2.6.2.7 ShotNoise: "shot\_noise"

**Included by default:** True

**File Description:** apply poisson shot noise to images

**Class Description:** <no docstring>

### Changes:

- 

### Data

### Meta-data

```
filename : None
name : shot_noise
image_plane_id : 0
temperature : -230
dit : !OBS.dit
ndit : !OBS.ndit
element_name : micado_detector_array
z_order : [820]
include : True
random_seed : !SIM.random.seed
```

#### 2.6.2.8 PoorMansHxRGReadoutNoise: "readout\_noise"

**Included by default:** True

**File Description:** Readout noise frames

**Class Description:** <no docstring>

### Changes:

- 

### Data

### Meta-data

```
filename : None
name : readout_noise
image_plane_id : 0
temperature : -230
dit : !OBS.dit
ndit : !OBS.ndit
element_name : micado_detector_array
noise_std : 12
n_channels : 64
z_order : [811]
include : True
pedestal_fraction : 0.3
read_fraction : 0.4
line_fraction : 0.25
```

```
channel_fraction : 0.05  
  random_seed : !SIM.random.seed
```

## 2.7 OpticalElement: "MICADO\_simulation\_paramters"

**Element:** simulation

**Alias:** SIM

**Description:** RC simulation paramters which need to change for a MICADO run

### 2.7.1 Global properties

```
random : \{'seed': 9001\}
spectral : \{'wave_min': 0.7, 'wave_mid': 1.6, 'wave_max': 2.5\}
computing : \{'preload_field_of_view': True\}
reports : \{'preamble_file': '../docs/preamble.rst'\}
element_name : MICADO_simulation_paramters
```

### 2.7.2 Effects

Summary of Effects included in this optical element:

element	name	class	included	z_orders



## **Chapter 3**

# **MICADO Science package**

## 3.1 OpticalElement: "MICADO"

**Element:** instrument

**Alias:** INST

**Description:** base configuration for MICADO

### 3.1.1 Global properties

```
temperature : -190
filename_format : filters/TC_filter_{\}.dat
element_name : MICADO
```

### 3.1.2 Effects

Summary of Effects included in this optical element:

element	name	class	included	z_orders [3]
MICADO	micado_filter	FilterCurve	True	114 .. 514
MICADO	micado_common_optics	TERCurve	True	10 .. 510

#### 3.1.2.1 FilterCurve: "micado\_filter"

**Included by default:** True

**File Description:** transmission curve for filter

**Class Description:** Other Parameters

**Changes:**

- 

**Data**

**Meta-data**

```
filename : filters/TC_filter_Ks.dat
name : micado_filter
temperature : -190
filename_format : !INST.filename_format
element_name : MICADO
filter_name : !INST.filter_name
minimum_throughput : 0.000101
outer : 0.2
outer_unit : m
author : Ric Davies
```

```

        source : Ric Davies
    date_created : 2017-11-20
    date_modified : 2017-11-20
        status : Design - pre PDR list of filters
        type : filter:transmission
        center : 2.144876984095012
        width : 0.3470169216021642
    blue_cutoff : 1.97136852329393
    red_cutoff : 2.3183854448960943
    z_order : [114, 214, 514]
    include : True
    ignore_wings : False
        wave_min : !SIM.spectral.wave_min
        wave_max : !SIM.spectral.wave_max
    wave_unit : !SIM.spectral.wave_unit
    wave_bin : !SIM.spectral.spectral_resolution
        action : transmission
        position : -1
    wing_flux_level : None

```

### 3.1.2.2 TERCurve: "micado\_common\_optics"

**Included by default:** True

**File Description:** combined transmission for MICADO common optics

**Class Description:** Transmission, Emissivity, Reflection Curve

**Changes:**

- 

**Data**

**Meta-data**

```

        filename : TER_MICADO_IMG_common.dat
        name : micado_common_optics
    temperature : -190
    filename_format : filters/TC_filter_{\}.dat
    element_name : MICADO
        author : Auto-compiled from source
        source : LIST_MICADO_mirrors_static.dat
    date_created : 2020-08-25
    date_modified : 2020-08-25
        area : 0.19634954084936207
        area_unit : m2
    wavelength_unit : um
    emission_unit : photlam

```

```
    z_order : [10, 110, 510]
    include : True
ignore_wings : False
    wave_min : !SIM.spectral.wave_min
    wave_max : !SIM.spectral.wave_max
    wave_unit : !SIM.spectral.wave_unit
    wave_bin : !SIM.spectral.spectral_resolution
```

## 3.2 OpticalElement: "MICADO\_SCAO"

**Element:** instrument

**Alias:** INST

**Description:** MICADO SCAO mode effects

### 3.2.1 Global properties

```
psf : \{'strehl': 0.4, 'wavelength': 'Ks'\}  
element_name : MICADO_SCAO
```

### 3.2.2 Effects

Summary of Effects included in this optical element:

element	name	class	included	z_orders
MICADO_SCAO	scao_relay_optics_ter	TERCurve	True	[10, 110, 510]
MICADO_SCAO	scao_const_psf	AnisocadoConstPSF	True	[42]

#### 3.2.2.1 TERCurve: "scao\_relay\_optics\_ter"

**Included by default:** True

**File Description:** Combined TER curve for stand-alone relay optics module

**Class Description:** Transmission, Emissivity, Reflection Curve

**Changes:**

- 

**Data**

**Meta-data**

```
filename : TER_MICADO_RO.dat  
name : scao_relay_optics_ter  
psf : \{'strehl': 0.4, 'wavelength': 'Ks'\}  
element_name : MICADO_SCAO  
author : Auto-compiled from source  
source : LIST_RO_SCAO_mirrors.dat  
date_created : 2020-08-25  
date_modified : 2020-08-25  
area : 0.22061834409834324  
area_unit : m2  
wavelength_unit : um
```

```

emission_unit : photlam
    z_order : [10, 110, 510]
    include : True
ignore_wings : False
    wave_min : !SIM.spectral.wave_min
    wave_max : !SIM.spectral.wave_max
    wave_unit : !SIM.spectral.wave_unit
    wave_bin : !SIM.spectral.spectral_resolution

```

### 3.2.2.2 AnisocadoConstPSF: "scao\_const\_psf"

**Included by default:** True

**File Description:** field constant PSF as produced by stand-alone SCAO

**Class Description:** Makes a SCAO on-axis PSF with a desired Strehl ratio at a given wavelength

**Changes:**

- 

**Data**

**Meta-data**

```

        filename : MICADO_AnisoCADO_rms_map.fits
        name : scao_const_psf
        psf : \{'strehl': 0.4, 'wavelength': 'Ks'\}
    element_name : MICADO_SCAO
        strehl : !INST.psf.strehl
        wavelength : !INST.psf.wavelength
psf_side_length : 256
    offset : [0, 0]
    rounded_edges : True
    convolve_mode : full
        SIMPLE : True
        BITPIX : -64
        NAXIS : 2
        NAXIS1 : 35
        NAXIS2 : 9
        EXTEND : True
        CRVAL1 : 0
        CRVAL2 : 0.8
        CRPIX1 : 1.0
        CRPIX2 : 1.0
        CDELT1 : 20
        CDELT2 : 0.2
        CUNIT1 : nm
        CUNIT2 : um

```

```
CTYPE1 : LINEAR
CTYPE2 : LINEAR
LABEL1 : nmRMS
LABEL2 : wavelength
AUTHOR : Kieran Leschinski
DATE_CRE : 2019-07-30
DATE_MOD : 2019-07-30
SOURCE : AnisoCADO
STATUS : Strehl as a function of wavelength and wavefront error
ETypes : SRMAP
ECAT : -1
EDATA : 0
XOFFSET : 0
YOFFSET : 0
z_order : [42]
include : True
flux_accuracy : 0.001
sub_pixel_flag : False
wave_key : WAVE0
normalise_kernel : True
filter_filename_format : !INST.filename_format
```

### 3.3 OpticalElement: "MICADO\_MCAO"

**Element:** instrument

**Alias:** INST

**Description:** MICADO MCAO mode effects

#### 3.3.1 Global properties

```
psf : \{'strehl': 0.4, 'wavelength': 'Ks'\}  
element_name : MICADO_MCAO
```

#### 3.3.2 Effects

Summary of Effects included in this optical element:

element	name	class	included	z_orders
MICADO_MCAO	maory_mms_ter	TERCurve	True	[10, 110, 510]
MICADO_MCAO	maory_const_psf	AnisocadoConstPSF	True	[42]

##### 3.3.2.1 TERCurve: "maory\_mms\_ter"

**Included by default:** True

**File Description:** Combined TER curve for MAORY MMS relay optics module

**Class Description:** Transmission, Emissivity, Reflection Curve

**Changes:**

- 

**Data**

**Meta-data**

```
filename : TER_MAORY_MMS.dat  
name : maory_mms_ter  
psf : \{'strehl': 0.4, 'wavelength': 'Ks'\}  
element_name : MICADO_MCAO  
author : Auto-compiled from source  
source : LIST_mirrors_maory_mms.tbl  
date_created : 2020-08-25  
date_modified : 2020-08-25  
area : 0.9503317777109126  
area_unit : m2  
wavelength_unit : um
```



```

emission_unit : photlam
    z_order : [10, 110, 510]
    include : True
ignore_wings : False
    wave_min : !SIM.spectral.wave_min
    wave_max : !SIM.spectral.wave_max
    wave_unit : !SIM.spectral.wave_unit
    wave_bin : !SIM.spectral.spectral_resolution

```

### 3.3.2.2 AnisocadoConstPSF: "maory\_const\_psf"

**Included by default:** True

**File Description:** field constant PSF as produced by MAORY

**Class Description:** Makes a SCAO on-axis PSF with a desired Strehl ratio at a given wavelength

**Changes:**

- 

**Data**

**Meta-data**

```

        filename : MICADO_AnisoCADO_rms_map.fits
        name : maory_const_psf
        psf : \{'strehl': 0.4, 'wavelength': 'Ks'\}
    element_name : MICADO_MCAO
        strehl : !INST.psf.strehl
        wavelength : !INST.psf.wavelength
psf_side_length : 256
    offset : [0, 0]
    rounded_edges : True
    convolve_mode : full
        SIMPLE : True
        BITPIX : -64
        NAXIS : 2
        NAXIS1 : 35
        NAXIS2 : 9
        EXTEND : True
        CRVAL1 : 0
        CRVAL2 : 0.8
        CRPIX1 : 1.0
        CRPIX2 : 1.0
        CDELT1 : 20
        CDELT2 : 0.2
        CUNIT1 : nm
        CUNIT2 : um

```

```
CTYPE1 : LINEAR
CTYPE2 : LINEAR
LABEL1 : nmRMS
LABEL2 : wavelength
AUTHOR : Kieran Leschinski
DATE_CRE : 2019-07-30
DATE_MOD : 2019-07-30
SOURCE : AnisoCADO
STATUS : Strehl as a function of wavelength and wavefront error
ETYPE : SRMAP
ECAT : -1
EDATA : 0
XOFFSET : 0
YOFFSET : 0
z_order : [42]
include : True
flux_accuracy : 0.001
sub_pixel_flag : False
wave_key : WAVE0
normalise_kernel : True
filter_filename_format : !INST.filename_format
```

### 3.4   OpticalElement: "4mas"

**Element:** instrument

**Alias:** INST

**Description:** wide-field imager : 4mas/pix

#### 3.4.1   Global properties

```
filter_name : Ks
pixel_scale : 0.004
plate_scale : 0.266666666666
element_name : 4mas
```

#### 3.4.2   Effects

Summary of Effects included in this optical element:

element	name	class	included	z_orders

### 3.5    **OpticalElement: "1.5mas"**

**Element:** instrument

**Alias:** INST

**Description:** zoom imager : 1.5mas/pix

#### 3.5.1    **Global properties**

filter_name	: Ks
pixel_scale	: 0.0015
plate_scale	: 0.1
element_name	: 1.5mas

#### 3.5.2    **Effects**

Summary of Effects included in this optical element:

element	name	class	included	z_orders

## **Chapter 4**

# **Supoort packages**

## 4.1 OpticalElement: "armazones"

**Element:** atmosphere

**Alias:** ATMO

**Description:** Atmosphere and location details for Cerro Armazones

### 4.1.1 Global properties

```
altitude : 3060
longitude : -70.1918
latitude : -24.5899
temperature : 7
humidity : 0.1
pressure : 0.755
pwv : 2.5
airmass : !OBS.airmass
pupil_angle : !OBS.pupil_angle
pixel_scale : !INST.pixel_scale
element_name : armazones
```

### 4.1.2 Effects

Summary of Effects included in this optical element:

element	name	class	included	z_orders
armazones	armazones_atmo_default_ter_curve	AtmosphericTERCurve	True	[111, 511]
armazones	armazones_atmo_dispersion	AtmosphericDispersion	True	[231]
armazones	armazones_atmo_skycalc_ter_curve	SkycalcTERCurve	False	[112, 512]

#### 4.1.2.1 AtmosphericTERCurve: "armazones\_atmo\_default\_ter\_curve"

**Included by default:** True

**File Description:** atmospheric emission and transmission

**Class Description:** <no docstring>

**Changes:**

- 2019-07-24 (KL) Created file
- 2019-08-09 (KL) Updated values for airmass 1.2, pwv 2.5

**Data**

**Meta-data**

```

        filename : TER_armazones_default_NIR_IMG.dat
          name : armazones_atmo_default_ter_curve
          include : True
          altitude : 3060
          longitude : -70.1918
          latitude : -24.5899
        temperature : 7
          humidity : 0.1
          pressure : 0.755
            pwv : 2.5
          airmass : !OBS.airmass
        pupil_angle : !OBS.pupil_angle
        pixel_scale : !INST.pixel_scale
        element_name : armazones
          author : Kieran Leschinski
          source : skycalc website for standard Armazones conditions
        date_created : 2019-07-24
        date_modified : 2019-08-09
          status : Design
          type : atmosphere:ter_curve
          season : entire year
          time : entire night
          action : transmission
        wavelength_unit : um
        emission_unit : ph s-1 m-2 um-1 arcsec-2
          z_order : [111, 511]
        ignore_wings : False
          wave_min : !SIM.spectral.wave_min
          wave_max : !SIM.spectral.wave_max
          wave_unit : !SIM.spectral.wave_unit
          wave_bin : !SIM.spectral.spectral_resolution
            area : !TEL.area
          area_unit : m2
          position : 0

```

#### 4.1.2.2 AtmosphericDispersion: "armazones\_atmo\_dispersion"

**Included by default:** True

**File Description:** atmospheric dispersion

**Class Description:** Used to generate the wavelength bins based on shifts due to the atmosphere

**Changes:**

- 

**Data**

## Meta-data

```
filename : None
  name : armazones_atmo_dispersion
altitude : 3060
longitude : -70.1918
latitude : -24.5899
temperature : 7
humidity : 0.1
pressure : 0.755
  pwv : 2.5
  airmass : !OBS.airmass
pupil_angle : !OBS.pupil_angle
pixel_scale : !INST.pixel_scale
element_name : armazones
  z_order : [231]
  include : True
  wave_min : !SIM.spectral.wave_min
  wave_mid : !SIM.spectral.wave_mid
  wave_max : !SIM.spectral.wave_max
sub_pixel_fraction : !SIM.sub_pixel.fraction
num_steps : 1000
```

### 4.1.2.3 SkycalcTERCurve: "armazones\_atmo\_skycalc\_ter\_curve"

**Included by default:** False

**File Description:** atmospheric spectra pulled from the skycalc server

**Class Description:** <no docstring>

**Changes:**

- 

## Data

## Meta-data

```
filename : None
  name : armazones_atmo_skycalc_ter_curve
  include : False
altitude : 3060
longitude : -70.1918
latitude : -24.5899
temperature : 7
humidity : 0.1
pressure : 0.755
```



```
        pwv : 2.5
        airmass : !OBS.airmass
        pupil_angle : !OBS.pupil_angle
        pixel_scale : !INST.pixel_scale
    element_name : armazones
    observatory : armazones
        wmin : 699.9999999999999
        wmax : 2499.9999999999995
        wunit : um
        wdelta : 0.09999999999999999
        z_order : [112, 512]
    ignore_wings : False
        wave_min : !SIM.spectral.wave_min
        wave_max : !SIM.spectral.wave_max
        wave_unit : !SIM.spectral.wave_unit
        wave_bin : !SIM.spectral.spectral_resolution
        action : transmission
        area : !TEL.area
    area_unit : m2
    position : 0
```

## 4.2 OpticalElement: "ELT"

**Element:** telescope

**Alias:** TEL

**Description:** The extremely large telescope

### 4.2.1 Global properties

```
temperature : !ATMO.temperature
element_name : ELT
```

### 4.2.2 Effects

Summary of Effects included in this optical element:

element	name	class	included	z_orders
ELT	scope_surface_list	SurfaceList	True	[20, 120, 520]
ELT	scope_vibration	Vibration	True	[244, 744]
ELT	eso_combined_reflection	TERCurve	False	[10, 110, 510]

#### 4.2.2.1 SurfaceList: "scope\_surface\_list"

**Included by default:** True

**File Description:** list of ELT surfaces

**Class Description:** <no docstring>

**Changes:**

- 2018-11-19 (KL) Added meta data, added Action column
- 2019-01-28 (KL) Fixed YAML format in meta data
- 2020-08-17 (KL) Updated M1 and M4 dimensions according to ESO-253082\_4 sect 4.7 "all-glass" diameter
- 2020-08-17 (KL) Pegged temperature to the atmosphere

**Data**

**Meta-data**

```
filename : LIST_mirrors_EL.T.tbl
name : scope_surface_list
temperature : !ATMO.temperature
element_name : ELT
```

```

        author : Oliver Czoske, Kieran Leschinski
        source : ESO ELT DRM, ESO-253082_4
    date_created : 2018-11-19
    date_modified : 2020-08-17
        status : Design - pre MICADO-FDR mirror list
        outer_unit : m
        inner_unit : m
        angle_unit : degree
    temperature_unit : deg_C
        notes : ['2020-08-17 (KL) Coatings match those described in ESO-2
        z_order : [20, 120, 520]
        include : True
    ignore_wings : False
        wave_min : !SIM.spectral.wave_min
        wave_max : !SIM.spectral.wave_max
        wave_unit : !SIM.spectral.wave_unit
        wave_bin : !SIM.spectral.spectral_resolution
    minimum_throughput : !SIM.spectral.minimum_throughput
        etendue : !TEL.etendue

```

#### 4.2.2.2 Vibration: "scope\_vibration"

**Included by default:** True

**File Description:** residual vibration of telescope

**Class Description:** Creates a wavelength independent kernel image

**Changes:**

- 

**Data**

**Meta-data**

```

        filename : None
        name : scope_vibration
    temperature : 7
    element_name : ELT
        fwhm : 0.001
    pixel_scale : 0.004
        z_order : [244, 744]
        include : True
    flux_accuracy : 0.001
    sub_pixel_flag : False
    convolve_mode : full
        wave_key : WAVE0
    normalise_kernel : True

```

```
width_n_fwhms : 4
```

#### 4.2.2.3 TERCurve: "eso\_combined\_reflection"

**Included by default:** False

**File Description:** single combined reflection curve for clean ELT 5 mirror combination

**Class Description:** Transmission, Emissivity, Reflection Curve

**Changes:**

- 2019-11-06 (KL) Converted from .xlsx to .dat file, added ScopeSim meta data
- 2020-07-09 (KL) Added inner and outer dimensions to meta, for use with MICADO-Sci
- 2020-08-17 (KL) Added emissivity column according to ESO-253082\_4, sect 4.12.2

**Data**

**Meta-data**

```
filename : TER_ELT_system_20190611.dat
name : eso_combined_reflection
include : False
temperature : !ATMO.temperature
element_name : ELT
temperture : !ATMO.temperature
author : R. Holzloehner
source : See ESO-306070 and ESO-293390 for background.
date_created : 2018-09-18
date_modified : 2019-06-11
type : TERCurve
status : design
action : reflection
outer : 37.3
outer_unit : m
inner : 11.1
inner_unit : m
wavelength_unit : um
notes : ['Baseline coatings.', 'Fresh coatings without contamination']
z_order : [10, 110, 510]
ignore_wings : False
wave_min : !SIM.spectral.wave_min
wave_max : !SIM.spectral.wave_max
wave_unit : !SIM.spectral.wave_unit
wave_bin : !SIM.spectral.spectral_resolution
```

## 4.3 OpticalElement: "MAORY"

**Element:** relay\_optics

**Alias:** RO

**Description:** MAORY AO relay module

### 4.3.1 Global properties

```
temperature : !ATMO.temperature
psf_filename : None
element_name : MAORY
```

### 4.3.2 Effects

Summary of Effects included in this optical element:

element	name	class	included	z_orders
MAORY	maory_surface_list	SurfaceList	True	[20, 120, 520]
MAORY	maory_generic_psf	FieldConstantPSF	True	[262, 662]

#### 4.3.2.1 SurfaceList: "maory\_surface\_list"

**Included by default:** True

**File Description:** list of surfaces in MAORY

**Class Description:** <no docstring>

**Changes:**

- 2018-11-19 (KL) Added meta data, changed Dichr. filename
- 2019-01-28 (KL) Fixed YAML format in meta data
- 2020-06-22 (KL) Obsolete. Use LIST\_mirrors\_maory\_mms.tbl from now on.

**Data**

**Meta-data**

```
filename : LIST_mirrors_MCAO_MAORY.tbl
name : maory_surface_list
temperature : !ATMO.temperature
psf_filename : None
element_name : MAORY
author : Kieran Leschinski
source : Ciliegi+ 2018 SPIE, "MAORY for ELT - preliminary design o
```

```

    date_created : 2018-11-19
    date_modified : 2018-11-19
        status : Design - pre PDR list of MAORY mirrors
        type : mirror:list
    outer_unit : m
    inner_unit : m
    angle_unit : degree
    temperature_unit : deg_C
        z_order : [20, 120, 520]
        include : True
    ignore_wings : False
        wave_min : !SIM.spectral.wave_min
        wave_max : !SIM.spectral.wave_max
        wave_unit : !SIM.spectral.wave_unit
        wave_bin : !SIM.spectral.spectral_resolution
    minimum_throughput : !SIM.spectral.minimum_throughput
        etendue : !TEL.etendue

```

#### 4.3.2.2 FieldConstantPSF: "maory\_generic\_psf"

**Included by default:** True

**File Description:** MAORY field varying MCAO PSF

**Class Description:** <no docstring>

**Changes:**

- 

**Data**

**Meta-data**

```

    filename : PSF_MCAO_ConstPSF_40_18_6.fits
        name : maory_generic_psf
    temperature : 7
    psf_filename : None
    element_name : MAORY
        warning : Default PSF is not Field Varying. See Documentation
        SIMPLE : True
        BITPIX : 8
        NAXIS : 0
        EXTEND : True
        AUTHOR : Kieran Leschinski
    DATE_CRE : 2019-07-30
    DATE_MOD : 2019-07-30
    SOURCE : AnisoCADO
    STATUS : Best guess for a MAORY ConstantPSF with AnisoCADO

```

```
        ETYPE : CONSTPSF
        ECAT  : -1
        EDATA : 1
        XOFFSET : 0
        YOFFSET : 0
        z_order : [262, 662]
        include : True
    flux_accuracy : 0.001
    sub_pixel_flag : False
    convolve_mode : full
        wave_key : WAVE0
    normalise_kernel : True
```

## 4.4 OpticalElement: "default\_ro"

**Element:** relay\_optics

**Alias:** RO

**Description:** Simple stand-alone relay optics module

### 4.4.1 Global properties

```
temperature : !ATMO.temperature
psf_filename : None
element_name : default_ro
```

### 4.4.2 Effects

Summary of Effects included in this optical element:

element	name	class	included	z_orders
default_ro	relay_psf	FieldConstantPSF	True	[262, 662]
default_ro	relay_surface_list	SurfaceList	True	[20, 120, 520]

#### 4.4.2.1 FieldConstantPSF: "relay\_psf"

**Included by default:** True

**File Description:** SCAO PSF

**Class Description:** <no docstring>

**Changes:**

- 

**Data**

**Meta-data**

```
filename : PSF_SCAO_ConstPSF_0_5off.fits
name : relay_psf
temperature : 7
psf_filename : None
element_name : default_ro
warning : Default PSF is NOT field varying. See documentation.
SIMPLE : True
BITPIX : 8
NAXIS : 0
EXTEND : True
```



```

AUTHOR : Kieran Leschinski
DATE_CRE : 2019-07-30
DATE_MOD : 2019-07-30
SOURCE : AnisoCADO
STATUS : Best guess for a standard observations
ETypes : CONSTPSF
ECAT : -1
EDATA : 1
XOFFSET : 0
YOFFSET : 5
z_order : [262, 662]
include : True
flux_accuracy : 0.001
sub_pixel_flag : False
convolve_mode : full
wave_key : WAVE0
normalise_kernel : True

```

#### 4.4.2.2 SurfaceList: "relay\_surface\_list"

**Included by default:** True

**File Description:** list of surfaces in the relay optics

**Class Description:** <no docstring>

**Changes:**

- 2018-11-19 (KL) Added meta data
- 2019-01-28 (KL) Fixed YAML format in meta data
- 2020-07-18 (KL) Added all 6 mirrors from the CM16 update pdf
- 2020-07-18 (KL) Pegged temperature to atmosphere

**Data**

**Meta-data**

```

filename : LIST_RO_SCAO_mirrors.dat
name : relay_surface_list
temperature : !ATMO.temperature
psf_filename : None
element_name : default_ro
author : Oliver Czoske, Kieran Leschinski
source : P12_RelayOptics_Status_2020-06-23-MICADO-CM16-RO-v2.pdf
date_created : 2018-11-19
date_modified : 2020-08-17
status : Design - pre FDR list of stand-alone SCAO relay optics mi
type : mirror:list

```

```
        outer_unit : m
        inner_unit : m
        angle_unit : degree
temperature_unit : deg_C
        z_order : [20, 120, 520]
        include : True
ignore_wings : False
        wave_min : !SIM.spectral.wave_min
        wave_max : !SIM.spectral.wave_max
        wave_unit : !SIM.spectral.wave_unit
        wave_bin : !SIM.spectral.spectral_resolution
minimum_throughput : !SIM.spectral.minimum_throughput
        etendue : !TEL.etendue
```